



HelixCore

Helix Core Server User Guide

2020.2
November 2020

PERFORCE

www.perforce.com



Copyright © 2014-2020 Perforce Software, Inc..

All rights reserved.

All software and documentation of Perforce Software, Inc. is available from www.perforce.com. You can download and use Perforce programs, but you can not sell or redistribute them. You can download, print, copy, edit, and redistribute the documentation, but you can not sell it, or sell any documentation derived from it. You can not modify or attempt to reverse engineer the programs.

This product is subject to U.S. export control laws and regulations including, but not limited to, the U.S. Export Administration Regulations, the International Traffic in Arms Regulation requirements, and all applicable end-use, end-user and destination restrictions. Licensee shall not permit, directly or indirectly, use of any Perforce technology in or by any U.S. embargoed country or otherwise in violation of any U.S. export control laws and regulations.

Perforce programs and documents are available from our Web site as is. No warranty or support is provided. Warranties and support, along with higher capacity servers, are sold by Perforce.

Perforce assumes no responsibility or liability for any errors or inaccuracies that might appear in this book. By downloading and using our programs and documents you agree to these terms.

Perforce and Inter-File Branching are trademarks of Perforce.

All other brands or product names are trademarks or registered trademarks of their respective companies or organizations.

Any additional software included within Perforce is listed in "[License Statements](#)" on page 204.

Contents

How to use this guide	11
Syntax conventions	11
Feedback	11
Other documentation	12
Earlier versions of this guide	12
What's new in this guide	13
2021.1	13
2020.2	13
2020.1	13
2019.2	13
2019.1	13
Installation	14
On Linux and OS X	14
On Windows	14
Overview	15
Fundamental parts of Helix Core server	15
File management	16
Changelists	17
Parallel development	17
Shared files	17
Branching: branches versus streams	17
Security	18
Organizing your work: jobs and labels	18
Scripting and reporting	19
Tutorial	20
Read me first	20
Make binaries executable, on UNIX and OS X	20
Create a working directory	21
Start up the shared server	21
Start up the command line client	22
Verify the connection to the server	22

Create a stream depot	23
Create your first stream	24
Define a client workspace and bind it to the stream	27
Populate a mainline stream	30
Edit files	33
Delete files	34
Sync files from the depot to your client workspace	36
Populate child streams	36
Basic tasks	37
Overview of initial tasks	38
Overview of recurring tasks	38
Initial tasks	39
Create a working directory	40
Log in to the shared server	40
Start up a shared server	40
Start up the command line client and verify the connection to the server	41
Create a stream depot	42
Create a mainline stream	43
Define a workspace and bind it to the stream	44
Populate the mainline stream	45
Recurring file-level tasks	46
Sync files	48
Add files	49
Add files outside of Helix server and then use p4 reconcile -k	51
Edit files and check in changes	51
Delete files	52
Revert files, to discard changes	52
Rename and move files	52
Diff files	53
Resolve conflicts	54
Changelist-related tasks	54
Submit a pending changelist	55
Create numbered changelists	56
Submit a numbered changelist	57
Undo a submitted change	57

Shelve changelists	57
Display information about changelists	59
Move files between changelists	60
Delete changelists	60
Other recurring tasks	60
Configure client behavior	60
Configure stream behavior	60
Branch and populate child streams	61
Propagate changes	61
Configure clients	63
Configure the client process	64
Using the command line	64
Using config files	65
Using environment variables	66
Using the Windows registry or OS X system settings	67
Configure for IPv6 networks	67
Configure for Unicode	68
Configure a client workspace	69
How Helix server manages files in a workspace	70
Define a client workspace	70
Configure workspace options	72
Configure submit options	73
View a stream as of a specific changelist	74
Configure line-ending settings	75
Change the location and/or layout of your workspace	75
Manage workspaces	76
Delete a client workspace	77
Configure workspace views	78
Specify mappings	79
Use wildcards in workspace views	79
Map part of the depot	80
Map files to different locations in the workspace	80
Map files to different filenames	80
Rearrange parts of filenames	81
Exclude files and directories	81
Map a single depot path to multiple locations in a workspace	81
Restrict access by changelist	82

Avoid mapping conflicts	83
Automatically prune empty directories from a workspace	83
Map different depot locations to the same workspace location	83
Deal with spaces in filenames and directories	84
Map Windows workspaces across multiple drives	84
Use the same workspace from different computers	85
Streams	86
About streams	86
Configure a stream	87
Stream types	88
Merge down, copy up	89
Stream types - most stable to least stable	90
Task streams	90
Virtual streams	93
Stream views and paths	93
Stream paths and inheritance	96
Stream ParentView Examples	100
Update streams	106
Edit a stream	107
Resolve a stream	107
Revert a stream	107
Submit, shelve, and unshelve a stream	108
Resolve conflicts	109
How conflicts occur	109
How to resolve conflicts	110
Your, theirs, base, and merge files	110
Options for resolving conflicts	111
Accepting yours, theirs, or merge	112
Editing the merge file	113
Merging to resolve conflicts	113
Full list of resolve options	113
Resolving branched files, deletions, moves and filetype changes	115
Resolve command-line options	117
Resolve reporting commands	118
Codeline management	119

Organizing the depot	119
Branching streams (introduction)	120
A shortcut: p4 populate	121
Branching streams (merge)	121
When to branch	122
Branching streams	122
Merge changes	123
Merging between unrelated files	124
Merging specific file revisions	125
Re-merging and re-resolving files	125
Reporting branches and merges	125
Less common tasks	127
Work offline	127
Ignoring groups of files when adding	128
Locking files	128
Preventing multiple resolves by locking files	129
Preventing multiple checkouts	129
Security	131
SSL-encrypted connections	131
Connecting to services that require plaintext connections	133
Passwords	133
Setting passwords	133
Using your password	134
Connection time limits	134
Logging in and logging out	135
Working on multiple computers	135
Labels	136
Tagging files with a label	136
Untagging files	137
Previewing tagging results	137
Listing files tagged by a label	137
Listing labels that have been applied to files	137
Using a label to specify file revisions	137
Deleting labels	138
Creating a label for future use	139

Restricting files that can be tagged	139
Static versus automatic labels	140
Static labels	140
Automatic labels	141
Automatic labels: superior performance	143
Preventing inadvertent tagging and untagging of files	143
Using labels on edge servers	143
Using labels with Git	144
Jobs	145
Creating, editing, and deleting a job	145
Searching jobs	146
Searching job text	147
Searching specific fields	147
Using comparison operators	148
Searching date fields	149
Fixing jobs	149
Linking automatically	150
Linking manually	150
Linking jobs to changelists	151
Scripting and reporting	152
Common options used in scripting and reporting	152
Scripting with Helix server forms	153
File reporting	154
Displaying file status	155
Displaying file revision history	156
Listing open files	156
Displaying file locations	157
Displaying file contents	157
Displaying annotations (details about changes to file contents)	158
Monitoring changes to files	159
Changelist reporting	159
Listing changelists	159
Listing files and jobs affected by changelists	160
Label reporting	161
Branch and integration reporting	161

Job reporting	162
Listing jobs	162
Listing jobs fixed by changelists	162
System configuration reporting	163
Displaying users	163
Displaying workspaces	164
Listing depots	164
Sample script	164
Helix server file types	166
File type modifiers	167
Specifying how files are stored in Helix server	169
Assigning file types for Unicode files	170
Choosing the file type	170
Helix server file type detection and Unicode	171
Overriding file types	172
Preserving timestamps	172
Expanding RCS keywords	172
Helix server command syntax	174
Command-line syntax	174
Specifying filenames on the command line	177
Helix server wildcards	178
Restrictions on filenames and identifiers	179
Specifying file revisions	180
Reporting commands	183
Using Helix server forms	184
Glossary	185
License Statements	204

How to use this guide

This getting started guide covers basic tasks for users and administrators, includes a Tutorial, and assumes your organization is using Streams rather than custom branching.

This section provides information on typographical conventions, feedback options, and additional documentation.

Syntax conventions

Helix documentation uses the following syntax conventions to describe command line syntax.

Notation	Meaning
<code>literal</code>	Must be used in the command exactly as shown.
<i>italics</i>	A parameter for which you must supply specific information. For example, for a <i>serverid</i> parameter, supply the ID of the server.
<code>-a -b</code>	Both <i>a</i> and <i>b</i> are required.
<code>{-a -b}</code>	Either <i>a</i> or <i>b</i> is required. Omit the curly braces when you compose the command.
<code>[-a -b]</code>	Any combination of the enclosed elements is optional. None is also optional. Omit the brackets when you compose the command.
<code>[-a -b]</code>	Any one of the enclosed elements is optional. None is also optional. Omit the brackets when you compose the command.
<code>...</code>	Previous argument can be repeated. <ul style="list-style-type: none">▪ <code>p4 [g-opts] streamlog [-l -L -t -m max] stream1 ...</code> means 1 or more stream arguments separated by a space▪ See also the use on <code>...</code> in Command alias syntax in the <i>Helix Core P4 Command Reference</i>

Tip

`...` has a different meaning for directories. See [Wildcards](#) in the *Helix Core P4 Command Reference*.

Feedback

How can we improve this manual? Email us at manual@perforce.com.

Other documentation

See <https://www.perforce.com/support/self-service-resources/documentation>.

Tip

You can also search for Support articles in the Perforce Knowledgebase.

Earlier versions of this guide

2020.2, 2020.1, 2018.2, 2018.1, 2017.2, 2017.1, 2016.2, 2015.2, 2015.1, 2014.2, 2014.1

What's new in this guide

2021.1

See the [Release Notes](#).

2020.2

It is now possible to choose whether a release, development, or mainline stream inherits views from its parent stream. For example, you might want to your release streams to remain unaffected when the parent stream updates certain files, such as libraries that might affect builds. See "[Stream ParentView Examples](#)" on page 100.

It is now possible to integrate stream spec changes across streams. This can be useful for `noinherit` streams as well as for custom, propagatable fields.

The `p4 istat` command has the `-As` and `-Af` options to report the integration status of the stream spec and the stream files.

See the [Release Notes](#).

2020.1

See the Release Notes at <https://www.perforce.com/perforce/r20.1/user/relnotes.txt>.

2019.2

Various bug fixes. See the Release Notes at <https://www.perforce.com/perforce/r19.2/user/relnotes.txt>.

2019.1

Improved control when updating a stream spec with the "Private editing of streams" feature. See "[Update streams](#)" on page 106.

For a complete list of what's new in this release, see the [release notes](#).

Installation

This chapter tells you how to install the Helix server Command-Line Client (**p4**) and the Helix Core server (**p4d**, also referred to as Helix server) on your computer.

Instructions vary by operating system.

On Linux and OS X	14
On Windows	14

On Linux and OS X

On Linux and OS X, download the server and command line client binaries into the `/usr/local/bin` directory.

1. Change into the download directory.

```
$ cd /usr/local/bin
```

2. Download the executable files from the Perforce website.

<https://www.perforce.com/downloads>

3. Make the server and client binaries executable, if they aren't already. For example, on Linux:

```
$ chmod +x p4d
```

```
$ chmod +x p4
```

On Windows

To install the Helix server (**p4d**) and Helix server command-line client (**p4**) on Windows, download and run the Helix server Windows installer from the Downloads page of the Perforce web site:

<https://www.perforce.com/downloads>

The Helix server installer walks you through the steps to install the Helix server (**p4d.exe**), the Helix server command-line client (**p4.exe**), and other Helix server Windows components.

Overview

This chapter provides an overview of the Helix server version control system.

Tip

Before reading this guide, read the "Basic concepts" chapter of *Solutions Overview: Helix Version Control System*.

This guide documents the command-line client *only*. For documentation on other clients, see the Perforce documentation website.

Fundamental parts of Helix Core server	15
File management	16
Changelists	17
Parallel development	17
Shared files	17
Branching: branches versus streams	17
Security	18
Organizing your work: jobs and labels	18
Scripting and reporting	19

Fundamental parts of Helix Core server

Helix server is an enterprise version management system in which you connect to a shared versioning server.

You sync files from a shared repository called the *depot* to get the latest version.

You edit files on your computer in your *workspace* (also known as a "client").


You manage files with the help of *changelists*.

You have the option of submitting to the depot any changes you make locally to make them available to other users.

The Helix Core server, also known as Helix server, or **p4d**, manages depots, which contain every revision of every file under version management. Files are organized into directory trees. The server also maintains a database of metadata that tracks the files and client activity: logs, user permissions, configuration values.

Helix server *clients* provide an interface that allows you to check files in and out of the depot, resolve conflicts, and track change requests.

Helix server includes a number of clients: a command-line client, a graphical user interface client, and various plug-ins that work with commercial IDEs and productivity software.



Helix server also supports a decentralized (“distributed”) workflow. See the “Basic concepts” chapter of [Solutions Overview: Helix Version Control System](#), and [Using Helix Core Server for Distributed Versioning](#) (DVCS).

File management

You use Helix server clients to manage a special area of your computer, called a *workspace*. Directories in the depot are mapped to directories in your workspace, which contain local copies of managed files. You always work on managed files in your workspace:

1. You populate your local workspace by syncing files from the depot.
2. You check the files out of the depot (and into your workspace).
3. You make changes to the files.
4. You check them back into the depot, also known as *submitting*.

5. If the changes you try to submit conflict with changes that other users, working in parallel with you, have already submitted, you must resolve conflicts as needed.

Changelists

The unit of file submission is the *changelist*; it is the means by which you check files in and out of the depot. A changelist must contain at least one file and may contain tens of thousands. A changelist is numbered and allows you to track all changes with respect to the contents of the depot: file modifications, the addition of a file, or the deletion of a file.

A changelist is the simplest way to organize your work. A changelist also represents the atomic unit of work in Helix server: if a changelist includes several files, changes for all the files are committed to the depot or none of the changes are. For example, if a network connection between the client and the server fails during changelist submission, the entire submit fails.

Parallel development

As with all version management systems, Helix server is designed to let multiple users work on the same files, codelines, or digital assets in parallel and then reconcile differences later. When conflicts occur, the system resolves them if the user cannot.

Helix server permits parallel development at two levels:

- At the file level, with shared files
- At the codeline level, with *branching*.

Shared files	17
Branching: branches versus streams	17

Shared files

Parallel development also happens when multiple users check the same file(s) out of the depot, work on them in parallel, and check them back into the depot by submitting them. At the time of submission, Helix server reports whether there are conflicts with other users' changes to the same file or files, and requires that any conflicts be resolved.

Branching: branches versus streams

In the course of a collaborative development project, you may find it useful to split off the codeline into multiple codelines, each having a distinct intended purpose. For example, when a certain milestone is reached in development, you may choose to copy the code—also known as *branching* it—into a new codeline for testing, thereby creating a QA *branch*. After it passes all tests, it is copied up to the Beta test line where it is subjected to real-world use. Later, you may choose to *merge* one or more of these new branches back into the main codeline.

Streams: branches with additional intelligence

Streams are like branches, but with additional intelligence built in.

Streams:

- provide clues of where and how to do branching and merging
- guide merging and branching actions that support stability and innovation
- are ideal for implementing the mainline branching model, in which less stable streams merge changes to keep up to date with their parents, then copy work to the parent when the work is stable enough to promote.
- eliminate much of the work needed to define branches, create workspaces, and manage merges
- enable the system to generate views for associated workspaces, eliminating the need for you to update views manually to reflect changes to your stream structure.

When you create a stream, you specify its type, information about the files it is associated with, its relationship to other streams, and how files are to be treated for branching and merging. The system uses the information you provide to encourage merging best practices and to track parallel development.

The stream type tells the system how stable the stream is relative to other streams.

The stream's path information tells the system:

- which files to populate the workspace with
- which files child streams are allowed to branch
- which changelist to lock the files at.

Parent labeling specifies how the stream relates to other streams in the system, helping to determine how change flows through the system.

Note

This guide assumes the reader is using streams, but notes where instructions differ for branch users.

Security

The Helix server command line client supports a number of security-related features, mostly having to do with SSL encryption.

Organizing your work: jobs and labels

In addition to using changelists and streams to organize your work, you can use two other methods: jobs and labels.

- *Jobs* provide lightweight issue tracking that integrates well with third party defect tracking and workflow systems. They allow you to track the status of a bug or an enhancement request. Jobs have a status and a creator and are associated with changelists that implement the bug fix or the enhancement.
- *Labels* are sets of tagged file revisions that allow you to handle a heterogeneous group of files as one unit. While a changelist refers only to the contents of a given set of files at the time they were submitted, a label can refer to a group of file revisions from different points in time. You might want to use labels to define the group of files contained in a particular release, to sync a set of files, to populate a workspace, or to specify a set of file revisions to be branched. You can also use a label as an alias for a changelist number, which makes it easier to remember the changelist and easier to refer to it in issuing commands.

Scripting and reporting

You can use client commands in scripts and for reporting purposes. For example, you could:

- merge and then resolve multiple files in one script
- use the UNIX Stream Editor (`sed`) in conjunction with a Helix server client command to create a job
- issue a command reporting all labels containing a specific file revision (or range)

Tutorial

This section walks you through a tutorial to help you get familiar with the most common tasks.

Read me first	20
Make binaries executable, on UNIX and OS X	20
Create a working directory	21
Start up the shared server	21
Start up the command line client	22
Verify the connection to the server	22
Create a stream depot	23
Create your first stream	24
Define a client workspace and bind it to the stream	27
Populate a mainline stream	30
Edit files	33
Delete files	34
Sync files from the depot to your client workspace	36
Populate child streams	36

Read me first

This tutorial is for users not experienced with Helix server. After working through this tutorial, you should understand the following:

- the basics of starting up a shared server and command line client
- getting a shared server and client communicating with each other
- adding, editing, deleting, and syncing files on your client computer
- checking those files into the server.

The sections that follow take you — step-by-step — through the tutorial.

Important

Before running this tutorial install the shared server and command client binaries onto *the same computer*. See "[Installation](#)" on [page 14](#) for instructions.

Make binaries executable, on UNIX and OS X

On UNIX and OS X, make the server and client binaries executable, if they aren't already.

```
$ cd /usr/local/bin
$ chmod +x p4d
$ chmod +x p4
```

Create a working directory

Create a working directory in which to perform the rest of the steps in this tutorial, and then change to that directory. In this example, we create a directory called *tutorial* in the user's home directory.

On Unix and OS X

```
$ mkdir /Users/bruno/tutorial
$ cd /Users/bruno/tutorial
```

On Windows

```
$ mkdir C:\Users\bruno\tutorial
$ cd C:\Users\bruno\tutorial
```

Start up the shared server

1. Make a subdirectory in which to start up the server and client.

When started, the server creates a large number of database files; it's best not to clutter your working directory with these files, so we will start up the server and client in a designated directory.

On Unix and OS X

```
$ mkdir /Users/bruno/server
```

On Windows

```
$ mkdir C:\Users\bruno\server
```

2. Start up the shared server.

Start up the shared server, using the `-r dir` option to specify the directory created in the previous step and the `-p port` option to set the hostname:port number to `localhost:1666`, the required setting for running the shared server and the client on same computer.

On UNIX and OS X

```
$ p4d -r /Users/bruno/server -p localhost:1666
```

On Windows

```
$ p4d -r C:\Users\bruno\server -p localhost:1666
```

This produces the following output:

```
Perforce db files in 'server' will be created if missing...
Perforce Server starting...
```

Because the shared server runs in the foreground, you must **open a new terminal window** in which to run subsequent commands.

Start up the command line client

1. Change to your working directory.

This is the working directory you created in "Create a working directory" on the previous page.

On UNIX and OS X

```
$ cd /Users/bruno/tutorial
```

On Windows

```
$ cd C:\Users\bruno\tutorial
```

2. Set the P4PORT environment variable

The server is running as `localhost` on port 1666. For the client to communicate with the server, you must set the client's `P4PORT` variable to `localhost:1666`.

On UNIX and OSX with the bash shell:

```
$ export P4PORT=localhost:1666
```

On Windows

```
$ p4 set P4PORT=localhost:1666
```

3. Start up the command line client.

```
$ p4
```

This produces the following output, followed by a list of help commands.

```
Perforce -- the Fast Software Configuration Management System.
```

```
p4 is Perforce's client tool for the command line.
```

Verify the connection to the server

To verify a connection, run the `p4 info` command.

```
$ p4 info
```

If `P4PORT` is set correctly, information like the following is displayed:

```
User name: bruno
```

```
Client name: dhcp-133-n101
```

```
Client host: dhcp-133-n101.dhcp.perforce.com
```

```
Client unknown.
Current directory: /Users/bruno/tutorial
Peer address: 127.0.0.1:49917
Client address: 127.0.0.1
Server address: localhost:1666
Server root: /Users/bruno/server
Server date: 2016/03/01 16:15:38 -0800 PST
Server uptime: 00:03:26
Server version: P4D/DARWIN90X86_64/2015.2/1340214 (2016/02/03)
Server license: none
Case Handling: insensitive
```

The **Server address** field shows the host to which **p4** connected and also displays the host and port number on which the Helix server is listening. If **P4PORT** is set incorrectly, you receive a message like the following:

```
Perforce client error:
  Connect to server failed; check $P4PORT.
  TCP connect to perforce:1666 failed.
  perforce: host unknown.
```

If you get the "host unknown" error, speak to your administrator.

Create a stream depot

Note

For an introduction to streams, see the "Streams" on page 86 chapter.

Create a stream depot in which the stream you create in the next step will reside.

1. At the command line, type the following:

```
$ p4 depot -t stream JamCode
```

The **-t** option specifies the type of depot to create, in this case a stream depot. **JamCode** is the name of the depot you're creating.

2. Notice that the depot specification opens in your text editor:

```
# A Perforce Depot Specification.
#
# Depot:          The name of the depot.
```

```

# Owner:          The user who created this depot.
# Date:           The date this specification was last modified.
# Description:    A short description of the depot (optional).
# Type:           Whether the depot is 'local', 'remote',
#                 'stream', 'spec', 'archive', 'tangent',
#                 or 'unload'. Default is 'local'.
# Address:        Connection address (remote depots only).
# Suffix:         Suffix for all saved specs (spec depot only).
# StreamDepth:   Depth for streams in this depot (stream depots
only).
# Map:           Path translation information (must have ... in
it).
# SpecMap:       For spec depot, which specs should be recorded
(optional).
#
# Use 'p4 help depot' to see more about depot forms.

Depot:           JamCode
Owner:           bruno
Date:            2018/02/22 13:20:06
Description:
                 Created by bruno.

Type:            stream
StreamDepth:     //JamCode/1
Map:             JamCode/...

```

3. Regarding the **StreamDepth:** field, see "[Working with stream depots](#)" in *Helix Core P4 Command Reference*.
4. Save the file and exit the editor.
5. Notice that the command line now shows: **Depot JamCode saved.**

Create your first stream

A stream is where you store your work. The first stream is always a mainline stream. To learn more about streams, see "[Streams](#)" on page 86.

Tip

Helix Core server allows a stream to be re-parented to any other stream with the same depot root. Although it is possible to have multiple mainline streams in a stream depot, we recommend that you create only **one** mainline for each stream depot. Having a single mainline stream in a stream depot:

- avoids the possibility of accidentally re-parenting a child stream to a different mainline than that from which the stream originated
- simplifies the visual representation in Helix Visual Client (P4V)

To create the stream:

1. Issue the `p4 stream` command, specifying the stream depot name followed by the stream name.

Here, we name the stream `main`, so its full name is `//JameCode/main`, and we use the `-t` option to specify the stream type as mainline:

```
$ p4 stream -t mainline //JamCode/main
```

Helix server opens the stream spec in an editor:

```
# A Perforce Stream Specification.
#
# Stream:          The stream field is unique and specifies the
#                  depot path.
# Update:          The date the specification was last changed.
# Access:          The date the specification was originally
#                  created.
# Owner:           The user who created this stream.
# Name:            A short title which may be updated.
# Parent:          The parent of this stream, or 'none' if Type is
#                  mainline.
# Type:            Type of stream provides clues for commands run
#                  between stream and parent. Five types include
#                  'mainline',
#                  'release', 'development' (default), 'virtual'
#                  and 'task'.
# Description:     A short description of the stream (optional).
# Options:         Stream Options:
#                  allsubmit/ownersubmit [un]locked
```

```

#                               [no]toparent [no]fromparent
mergedown/mergeany
# Paths:           Identify paths in the stream and how they are to
be
#                               generated in resulting clients of this stream.
#                               Path types are
share/isolate/import/import+/exclude.
# Remapped:       Remap a stream path in the resulting client
view.
# Ignored:        Ignore a stream path in the resulting client
view.
#
# Use 'p4 help stream' to see more about stream specifications
and command.

Stream: //JamCode/main

Owner:  bruno
Name:   main
Parent: none
Type:   mainline
Description:
        Created by bruno.

Options:          allsubmit unlocked notoparent nofromparent
mergedown
Paths:
        share ...

```

A stream spec defines the stream's name and location, its type, its parent stream, the files in the workspace view of workspaces bound to it, and other configurable behaviors. Note that the stream name is composed of the stream depot name followed by the stream name. You edit the stream spec's fields to configure the stream's behavior, as explained in ["Configure a stream" on page 87](#).

2. Save the file and exit the editor.
3. Notice that the command line now shows **Stream //JamCode/main saved**.

4. To verify that your mainline stream has been created, issue the `p4 streams` command to display a list of streams.

```
$ p4 streams //JamCode/...
```

This produces the following output:

```
Stream //JamCode/main mainline none 'main'
```

Define a client workspace and bind it to the stream

A client workspace is the set of directories on your local computer where you work on the file revisions that Helix server manages. At minimum, you should assign your workspace a name and specify a workspace root where you want local copies of depot files stored. The client workspace name defaults to the hostname of the computer on which your client is running. For details, see ["Configure a client workspace" on page 69](#).

Before you can work in a stream, you must associate your workspace with the stream. When you associate a workspace with a stream, Helix server generates the *workspace view* based on the structure of the stream. Workspace views are a crucial concept in Helix server and are discussed in detail in ["Configure workspace views" on page 78](#).

To create a workspace and bind it to a stream:

1. Set the `P4CLIENT` environment variable to desired workspace name.

On UNIX and OS X

```
$ export P4CLIENT=bruno_ws
```

On Windows

```
$ set P4CLIENT=bruno_ws
```

2. Use the `p4 client` command to bind your workspace to the stream.

```
$ p4 client -S //JamCode/main
```

The `-S` option specifies the name of the associated stream.

Helix server opens the client specification (spec) in an editor:

```
# A Perforce Client Specification.
#
# Client:      The client name.
# Update:     The date this specification was last modified.
# Access:     The date this client was last used in any way.
# Owner:      The Perforce user name of the user who owns the
client
```

```
# workspace. The default is the user who created
the
# client workspace.
# Host: If set, restricts access to the named host.
# Description: A short description of the client (optional).
# Root: The base directory of the client workspace.
# AltRoots: Up to two alternate client workspace roots.
# Options: Client options:
# [no]allwrite [no]clobber [no]compress
# [un]locked [no]modtime [no]rmdir
# SubmitOptions:
# submitunchanged/submitunchanged+reopen
# revertunchanged/revertunchanged+reopen
# leaveunchanged/leaveunchanged+reopen
# LineEnd: Text file line endings on client:
local/unix/mac/win/share.
# Type: Type of client: writeable/readonly.
# Backup: Client's participation in backup enable/disable.
If not
# specified backup of a writable client defaults to
enabled.
# ServerID: If set, restricts access to the named server.
# View: Lines to map depot files into the client
workspace.
# ChangeView: Lines to restrict depot files to specific
changelists.
# Stream: The stream to which this client's view will be
dedicated.
# (Files in stream paths can be submitted only by
dedicated
# stream clients.) When this optional field is set,
the
# View field will be automatically replaced by a
stream
```

```
#           view as the client spec is saved.
# StreamAtChange:  A changelist number that sets a back-in-time
view of a
#           stream ( Stream field is required ).
#           Changes cannot be submitted when this field
is set.
#
# Use 'p4 help client' to see more about client views and
options.

Client:      bruno_ws

Owner:      bruno

Host:      dhcp-133-n101.dhcp.perforce.com

Description:
           Created by bruno.

Root:      /Users/bruno/tutorial

Options:    noallwrite noclobber nocompress unlocked
nomodtime normdir

SubmitOptions:  submitunchanged

LineEnd:    local

Stream:     //JamCode/main

View:
           //JamCode/main/... //bruno_ws/...
```

At this point you have the option to configure the workspace root directory and any other desired settings. The workspace root is the highest-level directory of the workspace under which the managed source files reside. For more information, see ["Define a client workspace" on page 70](#). Once you've done this, save any changes and quit the editor.

For information about configuring other settings, see ["Configure workspace views" on page 78](#).

3. Verify that your workspace has been created, with the `p4 clients` command.

```
$ p4 clients -S //JamCode/main
```

This produces the following output:

```
Client bruno_ws 2016/02/22 root /Users/bruno/tutorial 'Created by
bruno.'
```

Next, populate the mainline stream with files.

Populate a mainline stream

Now that you've created a stream, you can populate it with files. There are two ways to populate a mainline stream:

- Add files from the local filesystem.
- Branch files from another depot.

In this tutorial, we demonstrate populating by adding files. For information on populating by branching from another depot, see ["Branch from other depots" on page 45](#).

To add files to the mainline stream, copy the files and folders to the workspace root directory and then mark them for add with the `p4 add` command.

1. Copy the files and folders to the workspace root directory.

In this example, we add all files residing in a directory named `/Users/bruno/repository`.

On UNIX and OSX

```
$ cp /Users/bruno/repository/* /Users/bruno/tutorial
```

On Windows

```
$ copy C:\Users\bruno\repository\* C:\Users\bruno\tutorial
```

2. Change into the client workspace root directory.

On UNIX and OSX

```
$ cd /Users/bruno/tutorial
```

On Windows

```
$ cd C:\User\bruno\tutorial
```

3. Mark the files for add.

```
$ p4 add *
```

This creates a default **changelist**, which you will use when you submit to the depot the file you added to your workspace. For more information on changelists, see ["Changelist-related tasks" on page 54](#).

4. Submit the added files.

To populate the stream, submit the default changelist in which the files are open for add.

```
$ p4 submit
```

Helix server opens the **change specification** in an editor:

```
# A Perforce Change Specification.
#
# Change:      The change number. 'new' on a new changelist.
# Date:       The date this specification was last modified.
# Client:     The client on which the changelist was created.  Read-
only.
# User:       The user who created the changelist.
# Status:     Either 'pending' or 'submitted'. Read-only.
# Type:       Either 'public' or 'restricted'. Default is 'public'.
# Description: Comments about the changelist.  Required.
# ImportedBy: The user who fetched or pushed this change to this
server.
# Identity:   Identifier for this change.
# Jobs:       What opened jobs are to be closed by this changelist.
#             You may delete jobs from this list.  (New changelists
only.)
# Files:      What opened files from the default changelist are to
be added
#             to this changelist.  You may delete files from this
list.
#             (New changelists only.)

Change: new

Client: bruno_ws
```

```
User:   bruno

Status: new

Description:
    <enter description here>

Files:
    //JamCode/main/file1.cc      # add
    //JamCode/main/file1.h # add
    //JamCode/main/file1.txt     # add
    //JamCode/main/file2.cc      # add
    //JamCode/main/file2.h # add
    //JamCode/main/file2.txt     # add
    //JamCode/main/file3.cc      # add
    //JamCode/main/file3.h # add
    //JamCode/main/file3.txt     # add
```

Enter a description under **Description** and then save your changes, to store the files you added in the Helix server depot. Something like the following output is displayed:

```
Change 1 created with 9 open file(s).
Submitting change 1.
Locking 9 files ...
add //JamCode/main/file1.cc#1
add //JamCode/main/file1.h#1
add //JamCode/main/file1.txt#1
add //JamCode/main/file2.cc#1
add //JamCode/main/file2.h#1
add //JamCode/main/file2.txt#1
add //JamCode/main/file3.cc#1
add //JamCode/main/file3.h#1
add //JamCode/main/file3.txt#1
Change 1 submitted.
```

The files you added are now stored in the Helix server depot.

Edit files

Now that the files are stored in the depot, you or others can check them out of the depot to edit them. To open files for edit, issue the `p4 edit` command, followed by the names(s) of the files you want to edit:

```
$ p4 edit file1.txt
```

This displays output like the following:

```
//JamCode/main/file1.txt#1 - opened for edit
```

Now you can edit the file in the editor of your choice and make changes. After you've made the desired changes, you submit the changelist associated with the file(s):

```
$ p4 submit
```

This opens a `change specification` in an editor:

```
#
# Change:      The change number. 'new' on a new changelist.
# Date:       The date this specification was last modified.
# Client:     The client on which the changelist was created. Read-
only.
# User:      The user who created the changelist.
# Status:    Either 'pending' or 'submitted'. Read-only.
# Type:     Either 'public' or 'restricted'. Default is 'public'.
# Description: Comments about the changelist. Required.
# ImportedBy: The user who fetched or pushed this change to this
server.
# Identity:  Identifier for this change.
# Jobs:     What opened jobs are to be closed by this changelist.
#           You may delete jobs from this list. (New changelists
only.)
# Files:    What opened files from the default changelist are to
be added
#           to this changelist. You may delete files from this
list.
#           (New changelists only.)

Change: new
```

```
Client: bruno_ws

User:   bruno

Status: new

Description:
    <enter description here>

Files:
    //JamCode/main/file1.txt      # edit
```

Enter a description under **Description** and then save your changes, to store the edits you made in the Helix server depot. Something like the following output is displayed:

```
Change 2 created with 1 open file(s).
Submitting change 2.
Locking 1 files ...
edit //JamCode/main/file1.txt#2
Change 2 submitted.
```

Delete files

Deleting files is more complicated than just deleting them from your filesystem. To mark files for delete, issue the **p4 delete** command. In this case, we choose to delete just the header files.

```
$ p4 delete *.h
```

Helix server displays the following:

```
//JamCode/main/file1.h#1 - opened for delete
//JamCode/main/file2.h#1 - opened for delete
//JamCode/main/file3.h#1 - opened for delete
```

As in ["Edit files" on the previous page](#), you issue the **p4 submit** command to have the deletion affect files in the depot:

```
$ p4 submit
```

Helix server opens the **change specification** in an editor:

```
# A Perforce Change Specification.
#
# Change:      The change number. 'new' on a new changelist.
```

Delete files

```
# Date:          The date this specification was last modified.
# Client:        The client on which the changelist was created.  Read-
only.
# User:          The user who created the changelist.
# Status:        Either 'pending' or 'submitted'.  Read-only.
# Type:          Either 'public' or 'restricted'.  Default is 'public'.
# Description:   Comments about the changelist.  Required.
# ImportedBy:   The user who fetched or pushed this change to this
server.
# Identity:     Identifier for this change.
# Jobs:         What opened jobs are to be closed by this changelist.
#               You may delete jobs from this list.  (New changelists
only.)
# Files:        What opened files from the default changelist are to
be added
#               to this changelist.  You may delete files from this
list.
#               (New changelists only.)

Change: new

Client: jschaffer_ws

User:   jschaffer

Status: new

Description:
    <enter description here>

Files:
    //JamCode/main/file1.h # delete
    //JamCode/main/file2.h # delete
    //JamCode/main/file3.h # delete
```

Enter a description under **Description** and then save your changes, to store the changes you made in the Helix server depot. Something like the following output is displayed:

```
Change 3 created with 3 open file(s).
Submitting change 3.
Locking 3 files ...
delete //JamCode/main/file1.h#2
delete //JamCode/main/file2.h#2
delete //JamCode/main/file3.h#2
Change 3 submitted.
```

Sync files from the depot to your client workspace

Syncing (retrieving files from the depot) — with the `p4 sync` command — specifies the files and directories you want to retrieve from the depot. You do this to obtain the latest changes —be they edits, adds, or deletes—that have been made by others and then submitted to the depot.

You can only sync files that are mapped in your workspace view. For more information on workspace views, see "[Configure workspace views](#)" on page 78.

```
$ p4 sync ...
```

By passing in `...`, we request to sync all files in the current directory.

Suppose that another user has made changes to `file1.cc` and `file3.cc`. A `sync` request, would yield output like the following:

```
//JamCode/main/file1.cc#3 - updating
/Users/bruno/workspace/tutorial/file1.cc
//JamCode/main/file3.cc#5 - updating
/Users/bruno/workspace/tutorial/file3.cc
```

Populate child streams

After populating the mainline, you can branch files for development and for release. For example, to create a development stream that is a clone of its mainline parent, issue the following command:

```
$ p4 stream -t development -P //JamCode/main //JamCode/dev
```

Helix server displays the stream specification with the type set to development. Save the specification. To populate the stream with the files from the mainline, issue the following commands:

```
$ p4 populate -d "From main" -S //JamCode/dev -r
$ p4 sync
```

Basic tasks

This chapter describes tasks you commonly perform when setting up and using your version control system. It discusses both tasks you perform just once when getting your system set up, and tasks you may perform one or more times during the lifetime of your installation.

Overview of initial tasks	38
Overview of recurring tasks	38
Initial tasks	39
Create a working directory	40
Log in to the shared server	40
Start up a shared server	40
Start up the command line client and verify the connection to the server	41
Create a stream depot	42
Create a mainline stream	43
Define a workspace and bind it to the stream	44
Populate the mainline stream	45
Recurring file-level tasks	46
Sync files	48
Add files	49
Add files outside of Helix server and then use <code>p4 reconcile -k</code>	51
Edit files and check in changes	51
Delete files	52
Revert files, to discard changes	52
Rename and move files	52
Diff files	53
Resolve conflicts	54
Changelist-related tasks	54
Submit a pending changelist	55
Create numbered changelists	56
Submit a numbered changelist	57
Undo a submitted change	57
Shelve changelists	57
Display information about changelists	59
Move files between changelists	60
Delete changelists	60
Other recurring tasks	60
Configure client behavior	60
Configure stream behavior	60
Branch and populate child streams	61
Propagate changes	61

Overview of initial tasks

This section gives you an overview of the tasks for setting up your command client and shared server. The tasks in this workflow should be performed once, and in the order presented in the following table:

Step	Task	Stream or classic user	Link
1	Create a working directory	Both	"Create a working directory" on page 40
2	Log in to the shared server or start up a shared server	Both	"Log in to the shared server" on page 40 or "Start up a shared server" on page 40
3	Start up the command line client and verify the connection to the server	Both	"Start up the command line client and verify the connection to the server" on page 41
4	Create a stream depot	Stream	"Create a stream depot" on page 42
5	Create a mainline stream	Stream. Classic users, see "Organizing the depot" on page 119.	"Create a mainline stream" on page 43
6	Define a workspace	Both	"Define a workspace and bind it to the stream" on page 44
7	Bind the workspace to the stream	Stream	"Define a workspace and bind it to the stream" on page 44
8	Populate the mainline stream	Stream. Classic users populate a codeline.	"Populate the mainline stream" on page 45

Overview of recurring tasks

This section gives you an overview of the tasks you perform during the lifetime of your installation, divided between file-level tasks and other tasks. You may perform them one or more times, or never.

The following table summarizes file-level recurring tasks:

Task	Stream or classic user	Link
Sync files from the depot	Both	"Sync files" on page 48

Task	Stream or classic user	Link
Edit files	Both	"Edit files and check in changes" on page 51
Rename and move files	Both	"Rename and move files" on page 52
Diff files	Both	"Diff files" on page 53
Revert files	Both	"Revert files, to discard changes" on page 52
Add files	Both	"Add files" on page 49
Delete files	Both	"Delete files" on page 52
Resolve conflicts	Both	"Resolve conflicts" on page 109

The following table summarizes other recurring tasks:

Task	Stream or classic user	Link
Work with changelists	Both	"Changelist-related tasks" on page 54
Configure client behavior	Both	"Configure clients" on page 63
Configure stream behavior	Stream	"Configure a stream" on page 87
Branch and populate child streams	Stream	"Branch and populate child streams" on page 61
Propagate changes between streams	Stream	"Propagate changes" on page 61

Initial tasks

You perform the tasks in this section once, in the order presented.

Create a working directory	40
Log in to the shared server	40
Start up a shared server	40
Start up the command line client and verify the connection to the server	41
Create a stream depot	42
Create a mainline stream	43
Define a workspace and bind it to the stream	44
Populate the mainline stream	45

Create a working directory

Create a working directory and then change to the directory. In this example, we create a working directory called *work* in the user's home directory.

```
$ mkdir /Users/bruno/work
$ cd /Users/bruno/work
```

Log in to the shared server

Typically, your administrator starts up a shared server for you. If you need to start up your own shared server, see "[Start up a shared server](#)" below.

Your admin provides you with a user id, a password, and the server's address. You then follow these steps:

1. Set the P4PORT environment variable to the server address the admin gave you.

Suppose the server is running as `server1` on port 1666. To enable the client to communicate with the server, set the client's `P4PORT` variable to `server1:1666`.

On UNIX and OSX

```
$ export P4PORT=server1:1666
```

On Windows

```
$ p4 set P4PORT=server1:1666
```

2. Log in to the server with the `p4 login` command.

```
$ p4 login
```

Helix server displays the following:

```
Enter password:
```

3. Enter the password your admin gave you.

Helix server displays the following:

```
User bruno logged in.
```

Start up a shared server

Download into your computer's `/usr/local/bin` directory the server (`p4d`) and client (`p4`) binaries, as described in "[Installation](#)" on [page 14](#). Then, follow these steps:

1. Make the server and client binaries executable, if they're not already

```
$ chmod +x /usr/local/bin/p4d
$ chmod +x /usr/local/bin/p4
```

2. Make a subdirectory in which to start up the server and client.

When started, the server creates a large number of database files. It's best not to clutter your working directory with these files, so we will start up the server and client in a different directory. Create a directory:

```
$ mkdir /Users/bruno/server
```

3. Start up the shared server, using the `-r dir` option to specify the directory created in the previous step.

```
$ p4d -r /Users/bruno/server
```

This produces the following output:

```
Perforce db files in 'server' will be created if missing...
Perforce Server starting...
```

Start up the command line client and verify the connection to the server

1. Start up the command line client:

```
$ p4
```

2. To verify a connection, issue the `p4 info` command. If `P4PORT` is set correctly, information like the following is displayed:

```
User name: bruno
Client name: bruno_ws
Client host: computer_12
Client root: c:\bruno_ws
Current directory: c:\bruno_ws
Peer address: 10.0.102.24:61122
Client address: 10.0.0.196
Server address: ssl:example.com:1818
Server root: /usr/depot/p4d
Server date: 2020/09/28 15:03:05 -0700 PDT
Server uptime: 752:41:33
```

```
Server version: P4D/FREEBSD/2012.1/406375 (2020/08/25)
ServerID: Master
Server license: P4Admin <p4adm> 20 users (expires 2021/01/01)
Server license-ip: 10.0.0.2
Case handling: sensitive
```

The **Server address**: field shows the host to which **p4** connected and also displays the host and port number on which the Helix server is listening. If **P4PORT** is set incorrectly, you receive a message like the following:

```
Perforce client error:
Connect to server failed; check $P4PORT.
TCP connect to perforce:1666 failed.
perforce: host unknown.
```

3. If the host:port value is **perforce:1666**, **P4PORT** has not been set. Set **P4PORT** and try to connect again.
4. If your installation requires SSL, make sure your **P4PORT** is of the form **ssl:hostname:port**.
5. You will be asked to verify the server's fingerprint the first time you attempt to connect to the server. If the fingerprint is accurate, use the **p4 trust** command to install the fingerprint into a file (pointed to by the **P4TRUST** environment variable) that holds a list of known/trusted Helix server and their respective fingerprints. If **P4TRUST** is unset, this file is **.p4trust** in the user's home directory. For more information, see "[SSL-encrypted connections](#)" on page 131.
6. If your installation requires plain text (in order to support older Helix server applications), set **P4PORT** to **tcp:hostname:port**.

Create a stream depot

Typically your administrator will create a stream depot for you and provide you with the depot name. However, if you are creating a stream depot yourself, type the following:

```
$ p4 depot -t stream depotname
```

The **-t** option of the **p4 depot** command specifies the type of depot to create, in this case a stream depot.

Helix server opens the depot specification in an editor:

```
# A Perforce Depot Specification.
#
# Depot:          The name of the depot.
# Owner:          The user who created this depot.
# Date:           The date this specification was last modified.
# Description:    A short description of the depot (optional).
```

```

# Type:          Whether the depot is 'local', 'remote',
#               'stream', 'spec', 'archive', 'tangent',
#               or 'unload'.  Default is 'local'.
# Address:       Connection address (remote depots only).
# Suffix:        Suffix for all saved specs (spec depot only).
# StreamDepth:  Depth for streams in this depot (stream depots only).
# Map:          Path translation information (must have ... in it).
# SpecMap:      For spec depot, which specs should be recorded
#               (optional).
#
# Use 'p4 help depot' to see more about depot forms.

Depot:          JamCode

Owner:          bruno

Date:           2016/02/22 13:20:06

Description:

                Created by bruno.

Type:           stream

StreamDepth:    //JamCode/1

Map:            JamCode/...

```

Adjust the value of other fields and save the specification.

Create a mainline stream

When you create a stream, you assign it to one of the ["Stream types" on page 88](#). To create a mainline stream:

1. Issue the `p4 stream` command, specifying the depot followed by the stream name.

For example:

```
$ p4 stream -t mainline //JamCode/main
```

The stream specification form is displayed.

2. Change options in the spec to assign the stream the characteristics you want and save the spec. For details on the stream spec, see ["Configure a stream" on page 87](#).
3. To verify that your mainline stream has been created, issue the `p4 streams` command.

For example:

```
$ p4 streams //JamCode/...
```

Define a workspace and bind it to the stream

Before you can work in a stream, you must define a workspace associated with the stream. When you associate a workspace with a stream, Helix server generates the *workspace view* based on the structure of the stream. Stream users never need edit the workspace view (and cannot manually alter it). If the structure of the stream changes, Helix server updates the views of workspaces associated with the stream on an as-needed basis.

Note

Users of a non-stream classic depot define a workspace by issuing the `p4 client` command *without* passing the `-S` option, and edit the workspace view manually by editing the **View:** field in the client spec. See ["Configure workspace views" on page 78](#).

Your Helix server administrator might have already configured a client workspace for your computer. If so, the **Client** field in the client spec displays the Client workspace name when the user issues the `p4 client` command.

If not, to create a workspace for a stream:

1. Issue the `p4 client` command, using the `-S` option to specify the name of the associated stream.

For example:

```
$ p4 client -S //JamCode/main
```

The workspace specification form is displayed.

2. Configure the workspace **Root** directory and any other desired settings, and save the specification. For details, see ["Define a client workspace" on page 70](#).
3. Verify that your workspace has been created by using `p4 clients`.

For example:

```
$ p4 clients -S //JamCode/main
```

The next step is ["Populate the mainline stream" on the facing page](#).

Populate the mainline stream

Note

Users of a non-stream classic depot populate a branch. See ["Codeline management"](#) on page 119.

There are two ways to populate a mainline stream:

- ["Add files" below](#) from the local filesystem. It does not preserve file history and is the most typical way.
- ["Branch from other depots" below](#). If you have existing non-stream classic depots and you need to preserve file history, use this way.

Add files

If you do not need to preserve file history, add the files. To add files to the mainline stream:

1. Create the workspace root directory if it does not exist.

For example:

```
C:\bruno_ws> cd C:\Users\bruno\p4clients
C:\Users\bruno\p4clients> mkdir bruno_projectX_main
```

2. Copy the files and folders to the workspace root directory.
3. Change into the client workspace root directory, and use the `p4 reconcile` command to detect files not under Helix server control and open them for add by using the `p4 add` command.

```
C:\Users\bruno\p4clients> cd bruno_projectX_main
C:\Users\bruno\p4clients\bruno_projectX_main> p4 add ...
```

To verify that the files are set up to be added correctly, issue the `p4 opened` command.

To populate the stream, submit the changelist in which the files are open.

For details on working with changelists, see ["Changelist-related tasks"](#) on page 54.

Branch from other depots

You can branch files from other stream depots, classic depots, or remote depots into a stream. If you populate the mainline by branching, Helix server preserves the connection between the revision history of the source and target files. Your workspace must be set to one associated with the target stream (example: `p4 set P4CLIENT=bruno_projectX_main`).

To populate the mainline by branching, issue the `p4 copy` command, specifying source and target. Example:

```
$ p4 copy -v //mysourcedepot/mainline/... //ProjectX/main/...
```

In this example, the `-v` option performs the copy on the server without syncing the newly-created files to the workspace. This can be a significant time-saver if there are many files being copied. You can then sync only the files you intend to work with from the new location.

`p4d` displays a series of “import from” messages listing the source and target files, and opens the file (s) in a pending changelist. To preview the results of the operation without opening files, specify the `-n` option.

To populate the stream with the files from the mainline, issue the following commands:

1. To verify that the files are set up to be added correctly, issue the `p4 opened` command.
2. To populate the stream, `p4 submit` the changelist in which the files are open.

If you are populating an empty stream, you can simplify this process by using `p4 populate`. For example:

```
$ p4 populate //mysourcedepot/mainline/... //ProjectX/main/...
```

does the same thing as `p4 copy -v` followed by a `p4 submit`.

Tip

To preview what the result of the command would be, first use `p4 populate -n`, and, if the result is what you want, use `p4 populate` without the `-n` preview.

To undo an erroneous copy operation, issue the `p4 revert` command. For example:

```
$ p4 revert //ProjectX/main/...
```

Recurring file-level tasks

This section describes tasks you perform during the lifetime of your installation that occur at the file level.

Before we look at the tasks in detail, here’s a table that provides a snapshot of the sequence in which you perform the most common file-related tasks.

For details on working with changelists, see ["Changelist-related tasks" on page 54](#).

Here are the basic steps for working with files. In general, to change files in the depot (file repository), you open the files in changelists and submit the changelists with a description of your changes. Helix server assigns numbers to changelists and maintains the revision history of your files. This approach enables you to group related changes and find out who changed a file and why and when it was changed.

Task	Description						
Syncing (retrieving files from the depot)	Issue the p4 sync command, specifying the files and directories you want to retrieve from the depot. You can only sync files that are mapped in your client workspace view.						
Add files to the depot	<ol style="list-style-type: none"> 1. Create the file in the workspace. 2. Open the file for add in a changelist (p4 add). 3. Submit the changelist (p4 submit). 						
Edit files and check in changes	<ol style="list-style-type: none"> 1. If necessary, sync the desired file revision to your workspace (p4 sync). 2. Open the file for edit in a changelist (p4 edit). 3. Make your changes. 4. Submit the changelist (p4 submit). To discard changes, issue the p4 revert command. 						
Delete files from the depot	<ol style="list-style-type: none"> 1. Open the file for delete in a changelist (p4 delete). The file is deleted from your workspace. 2. Submit the changelist (p4 submit). The file is deleted from the depot. 						
Discard changes	<p>Revert the files or the changelist in which the files are open. Reverting has the following effects on open files:</p> <table border="1"> <tbody> <tr> <td>Add</td> <td>no effect - the file remains in your workspace.</td> </tr> <tr> <td>Edit</td> <td>the revision you opened is resynced from the depot, overwriting any changes you made to the file in your workspace.</td> </tr> <tr> <td>Delete</td> <td>the file is resynced to your workspace.</td> </tr> </tbody> </table>	Add	no effect - the file remains in your workspace.	Edit	the revision you opened is resynced from the depot, overwriting any changes you made to the file in your workspace.	Delete	the file is resynced to your workspace.
Add	no effect - the file remains in your workspace.						
Edit	the revision you opened is resynced from the depot, overwriting any changes you made to the file in your workspace.						
Delete	the file is resynced to your workspace.						

Files are added to, deleted from, or updated in the depot only when you successfully submit the pending changelist in which the files are open. A changelist can contain a mixture of files open for add, edit and delete.

For details on working with changelists, see ["Changelist-related tasks" on page 54](#).

Also in this section:

Sync files	48
Add files	49
Add files outside of Helix server and then use p4 reconcile -k	51
Edit files and check in changes	51
Delete files	52

Revert files, to discard changes	52
Rename and move files	52
Diff files	53
Resolve conflicts	54

Sync files

Syncing—with the **p4 sync** command—adds, updates, or deletes files in the client workspace to bring the workspace contents into agreement with the depot. If a file exists within a particular subdirectory in the depot, but that directory does not exist in the client workspace, the directory is created in the client workspace when you sync the file. If a file has been deleted from the depot, **p4 sync** deletes it from the client workspace.

Example Sync files from the depot to a client workspace

The command below retrieves the most recent revisions of all files in the client view from the depot into the workspace. As files are synced, they are listed in the command output.

```
C:\bruno_ws> p4 sync
//Acme/dev/bin/bin.linux24x86/readme.txt#1 - added as c:\bruno_
ws\dev\bin\bin.linux24x86\readme.txt
//Acme/dev/bin/bin.ntx86/glut32.dll#1 - added as c:\bruno_
ws\dev\bin\bin.ntx86\glut32.dll
//Acme/dev//bin/bin.ntx86/jamgraph.exe#2 - added as c:\bruno_
ws\dev\bin\bin.ntx86\jamgraph.exe
[...]
```

Note

You cannot sync files that are not in your workspace view. See ["Configure workspace views"](#) on page 78 for more information.

To sync revisions of files prior to the latest revision in the depot, use revision specifiers. For example, to sync the first revision of **Jamfile**, which has multiple revisions, issue the following command:

```
$ p4 sync //Acme/dev/jam/Jamfile#1
```

To sync groups of files or entire directories, use wildcards. For example, to sync everything in and below the **jam** folder, issue the following command:

```
$ p4 sync //Acme/dev/jam/...
```

The Helix server tracks which revisions you have synced. For maximum efficiency, Helix server does not re-sync an already-synced file revision. To re-sync files you (perhaps inadvertently) deleted manually, specify the `-f` option when you issue the `p4 sync` command.

Add files

To add files to the depot, create the files in your workspace, then issue the `p4 add` command. The `p4 add` command opens the files for add in the default pending changelist. The files are added when you successfully submit the default pending changelist.

To open multiple files for add, use a single `p4 add` command with wildcards.

To add files recursively, use the Helix server `...` wildcard.

A similar approach is to use the `p4 reconcile -a *` command. The `p4 reconcile` command opens files for add, delete, or edit to reconcile a workspace with changes made outside of Helix server.

Example Add files

Bruno has created two text files that he must add to the depot. To add all the text files at once, he uses the `*` wildcard when he issues the `p4 add` command.

```
C:\bruno_ws\Acme\dev\docs\manuals> p4 add *.txt
//Acme/dev/docs/manuals/installnotes.txt#1 - opened for add
//Acme/dev/docs/manuals/requirements.txt#1 - opened for add
```

Now the files he wants to add to the depot are open in his default changelist. The files are stored in the depot when the changelist is submitted.

Example Add files with multiple *

Using the `*` wildcard in more than one place is possible.

```
C:\bruno_ws\Acme\dev\docs\manuals> p4 add *World*.*
//Acme/dev/docs/manuals/World.html#1 - opened for add
//Acme/dev/docs/manuals/WorldWorld.java#1 - opened for add
//Acme/dev/docs/manuals/TwoWorldsApart.json#1 - opened for add
```

Example Add files with ...

Using `...` allows you to add files in the specified directory and its subdirectories.

```
C:\bruno_ws\Acme\dev\docs\manuals> p4 add admin-guide/...
//Acme/dev/docs/manuals/admin-guide/readme.txt#1 - opened for add
//Acme/dev/docs/manuals/admin-guide/subdirectory1/procedure1.html#1
- opened for add
```

You can also issue the command without specifying any directory, in which case it applies to the current directory and its subdirectories:

```
C:\bruno_ws\Acme\dev\docs>manuals> p4 add ...
//Acme/dev/docs/manuals/admin-guide/readme.txt#1 - opened for add
//Acme/dev/docs/manuals/admin-guide/subdirectory1/procedure1.html#1
- opened for add
//Acme/dev/docs/manuals/developer-guide/readme.txt#1 - opened for
add
```

Example Submit a changelist to the depot

Bruno is ready to add his files to the depot. He types `p4 submit` and sees the following form in a standard text editor:

```
Change: new
Client: bruno_ws
User:   bruno
Status: new
Description:
    <enter description here>
Type:   public
Files:
    //Acme/dev/docs/manuals/installnotes.txt # add
    //Acme/dev/docs/manuals/requirements.txt # add
```

Bruno changes the contents of the **Description:** field to describe his file updates. When he's done, he saves the form and exits the editor, and the new files are added to the depot.

You must enter a description in the **Description:** field. You can delete lines from the **Files:** field. Any files deleted from this list are moved to the next default changelist, and are listed the next time you submit the default changelist.

If you are adding a file to a directory that does not exist in the depot, the depot directory is created when you successfully submit the changelist.

For details on working with changelists, see "[Changelist-related tasks](#)" on page 54.

Add files outside of Helix server and then use p4 reconcile -k

In certain situations, you may need to copy a very large number of files into your workspace from another user's workspace. Rather than doing this via Helix server, you may, for performance reasons, choose to copy them directly — via a snapshot, for example — from the other user's workspace into yours.

Once you've done this, you will need to:

- Inform Helix server that these files now exist on your client.
That is, you want to update your client's *have list* to reflect the actual contents of your workspace. See the `p4 have` page in *Helix Core P4 Command Reference* for details on have lists.
- Ensure that your workspace view contains mappings identical to those contained in the workspace view of the client you copied from
This ensures that Helix server doesn't think these files are new.

To do this, run the `p4 reconcile -k` command.

You can also ignore groups of files when adding. See "Ignoring groups of files when adding" on page 128 for details.

Edit files and check in changes

You must open a file for edit before you attempt to edit the file. When you open a file for edit—with the `p4 edit` command—Helix server enables write permission for the file in your workspace and adds the files to a changelist. If the file is in the depot but not in your workspace, you must sync it before you open it for edit.

Example Open a file for edit

Bruno wants to make changes to `command.c`, so he syncs it and opens the file for edit.

```
C:\bruno_ws\dev> p4 sync //Acme/dev/command.c
//depot/dev/command.c#8 - added as c:\bruno_ws\dev\command.c
```

```
C:\bruno_ws\dev> p4 edit //Acme/dev/command.c
//Acme/dev/command.c#8 - opened for edit
```

He then edits the file with any text editor. When he's finished, he submits the file to the depot with `p4 submit`.

Delete files

To delete files from the depot, you open them for delete by issuing the `p4 delete` command, then submit the changelist in which they are open. When you delete a file from the depot, previous revisions remain, and a new head revision is added, marked as “deleted.” You can still sync previous revisions of the file.

When you issue the `p4 delete` command, the files are deleted from your workspace but not from the depot. If you revert files that are open for delete, they are restored to your workspace. When you successfully submit the changelist in which they are open, the files are deleted from the depot.

Example Delete a file from the depot

Bruno deletes `vendor.doc` from the depot as follows:

```
C:\bruno_ws\dev> p4 delete //Acme/dev/docs/manuals/vendor.doc
//Acme/dev/docs/manuals/vendor.doc#1 - opened for delete
```

The file is deleted from the client workspace immediately, but it is not deleted from the depot until he issues the `p4 submit` command.

Revert files, to discard changes

To remove an open file from a changelist and discard any changes you made, issue the `p4 revert` command. When you revert a file, Helix server restores the last version you synced to your workspace. If you revert a file that is open for add, the file is removed from the changelist but is not deleted from your workspace.

Example Revert a file

Bruno decides not to add his text files after all.

```
C:\bruno_ws\dev> p4 revert *.txt
//Acme/dev/docs/manuals/installnotes.txt#none - was add, abandoned
//Acme/dev/docs/manuals/requirements.txt#none - was add, abandoned
```

To preview the results of a revert operation without actually reverting files, specify the `-n` option when you issue the `p4 revert` command.

Rename and move files

To rename or move files, you must first open them for add or edit, and then use the `p4 move` command:

```
C:\bruno_ws> p4 move source_file target_file
```

To move groups of files, use matching wildcards in the *source_file* and *target_file* specifiers. To move files, you must have Helix server **write** permission for the specified files. For information about using wildcards with Helix server files, see "[Helix server wildcards](#)" on page 178.

For details about Helix server permissions, see the [Helix Core Server Administrator Guide](#).

When you rename or move a file using **p4 move**, the versioning service creates an integration record that links it to its deleted predecessor, preserving the file's history. Integration is also used to create branches and to propagate changes.

Note

The **p4 move** command is renaming a file within the same directory, or moving a file between folders within the same directory tree. To learn how to restructure the depot by moving an entire branch, see the Knowledge Base article, "[Renaming Depot Directories](#)".

Diff files

Helix server allows you to *diff* (compare) revisions of text files. By diffing files, you can display:

- Changes that you made after opening the file for edit
- Differences between any two revisions
- Differences between file revisions in different branches

To diff a file that is synced to your workspace with a depot revision, issue the **p4 diff filename#rev** command. If you omit the revision specifier, the file in your workspace is compared with the revision you last synced, to display changes you made after syncing it.

To diff two revisions that reside in the depot but not in your workspace, use the **p4 diff2** command. To diff a set of files, specify wildcards in the filename argument when you issue the **p4 diff2** command.

The **p4 diff** command performs the comparison on your computer, but the **p4 diff2** command instructs the Helix server to perform the diff and to send the results to you.

The following table lists some common uses for diff commands:

To diff	Against	Use this command
The workspace file	The head revision	p4 diff file or p4 diff file#head
The workspace file	Revision 3	p4 diff file#3
The head revision	Revision 134	p4 diff2 file file#134
File revision at changelist 32	File revision at changelist 177	p4 diff2 file@32 file@177

To diff	Against	Use this command
The workspace file	A file shelved in pending changelist 123	<code>p4 diff file@=123</code>
All files in release 1	All files in release 2	<code>p4 diff2 //Acme/rel1/... //Acme/rel2/...</code>

By default, the `p4 diff` command launches Helix server's internal diff application. To use a different diff program, set the `P4DIFF` environment variable to specify the path and executable of the desired application. To specify arguments for the external diff application, use the `-d` option. For details, refer to the [Helix Core P4 Command Reference](#).

Resolve conflicts

When you and other users are working on the same set of files, conflicts can occur. Helix server enables your team to work on the same files simultaneously and resolve any conflicts that arise.

"Resolve conflicts" on page 109 explains in detail how to resolve file conflicts.

Changelist-related tasks

To change files in the depot, you open them in a *changelist*, make any changes to the files, and then *submit* the changelist. A changelist contains a list of files, their revision numbers, and the operations to be performed on the files. Unsubmitted changelists are referred to as *pending changelists*.

Submission of changelists is an all-or-nothing operation; that is, either all of the files in the changelist are updated in the depot, or, if an error occurs, none of them are. This approach guarantees that code alterations that affect multiple files occur simultaneously.

Helix server assigns numbers to changelists and also maintains a *default changelist*, which is numbered when you submit it. You can create multiple changelists to organize your work. For example, one changelist might contain files that are changed to implement a new feature, and another changelist might contain a bug fix. When you open a file, it is placed in the default changelist unless you specify an existing changelist number on the command line using the `-c` option. For example, to edit a file and submit it in changelist number 4, use `p4 edit -c 4 filename`. To open a file in the default changelist, omit the `-c` option.

You can also shelve changelists in order to temporarily preserve work in progress for your own use, or for review by others. Shelving enables you to temporarily cache files in the shared server without formally submitting them to the depot.

The Helix server might renumber a changelist when you submit it, depending on other users' activities; if your changelist is renumbered, its original number is never reassigned to another changelist.

You can restrict a changelist from public view by changing the `Type:` field from `public` to `restricted`. In general, if a changelist is restricted, only those users with `list` access to at least one of the files in the changelist are permitted to see the changelist description.

To control what happens to files in a changelist when you submit the changelist to the depot, see "Configure submit options" on page 73.

Also in this section:

Submit a pending changelist	55
Create numbered changelists	56
Submit a numbered changelist	57
Undo a submitted change	57
Shelve changelists	57
Display information about changelists	59
Move files between changelists	60
Delete changelists	60

Submit a pending changelist

To submit a pending changelist, issue the `p4 submit` command. When you issue the `p4 submit` command, a form is displayed, listing the files in the changelist. You can remove files from this list. The files you remove remain open in the default pending changelist until you submit them or revert them.

To submit specific files that are open in the default changelist, issue the `p4 submit filename` command. To specify groups of files, use wildcards. For example, to submit all text files open in the default changelist, type `p4 submit "*" .txt`. (Use quotation marks as an escape code around the `*` wildcard to prevent it from being interpreted by the local command shell).

After you save the changelist form and exit the text editor, the changelist is submitted to the Helix server, and the files in the depot are updated. After a changelist has been successfully submitted, only a Helix server administrator can change it, and the only fields that can be changed are the description and user name.

If an error occurs when you submit the default changelist, Helix server creates a numbered changelist containing the files you attempted to submit. You must then fix the problems and submit the numbered changelist using the `-c` option.

Helix server enables write permission for files that you open for edit and disables write permission when you successfully submit the changelist containing the files. To prevent conflicts with Helix server's management of your workspace, do not change file write permissions manually.

Before committing a changelist, `p4 submit` briefly locks all files being submitted. If any file cannot be locked or submitted, the files are left open in a numbered pending changelist. By default, the files in a failed submit operation are left locked unless the `submit.unlocklocked` configurable is set. Files are unlocked even if they were manually locked prior to submit if submit fails when `submit.unlocklocked` is set.

Create numbered changelists

To create a numbered changelist, issue the `p4 change` command. This command displays the changelist form. Enter a description and make any desired changes; then save the form and exit the editor.

All files open in the default changelist are moved to the new changelist. When you exit the text editor, the changelist is assigned a number. If you delete files from this changelist, the files are moved back to the default changelist.

Example Working with multiple changelists

Bruno is fixing two different bugs, and needs to submit each fix in a separate changelist. He syncs the head revisions of the files for the first fix and opens the file for edit in the default changelist:

```
C:\bruno_ws> p4 sync //JamCode/dev/jam/*.c
[list of files synced...]
```

```
C:\bruno_ws> p4 edit //JamCode/dev/jam/*.c
[...]
```

Now he issues the `p4 change` command and enters a description in the changelist form. After he saves the file and exits the editor, Helix server creates a numbered changelist containing the files.

```
C:\bruno_ws\dev\main\docs\manuals> p4 change
```

```
[Enter description and save form]
```

```
Change 777 created with 33 open file(s).
```

For the second bug fix, he performs the same steps, `p4 sync`, `p4 edit`, and `p4 change`. Now he has two numbered changelists, one for each fix.

The numbers assigned to submitted changelists reflect the order in which the changelists were submitted. When a changelist is submitted, Helix server might renumber it, as shown in the following example:

Example Automatic renumbering of changelists

Bruno has finished fixing the bug that he's been using changelist 777 for. After he created that changelist, he submitted another changelist, and two other users also submitted changelists. Bruno submits changelist 777 with `p4 submit -c 777`, and sees the following message:

```
Change 777 renamed change 783 and submitted.
```

Submit a numbered changelist

- To submit a numbered changelist, specify the `-c` option when you issue the `p4 submit` command.
- To submit the default changelist, omit the `-c` option.
- Using parallel submits can significantly improve performance.

See the `p4 submit` command in the Helix Core P4 Command Reference.

Undo a submitted change

One of the fundamental benefits of version control is the ability to undo an unwanted change, either to undo the effects of a bad changelist or to roll back to a known good changelist.

You use the `p4 undo` command to accomplish this. For details, refer to the `p4 undo` command description in the [Helix Core P4 Command Reference](#).

Shelve changelists

The Helix server shelving feature enables you to temporarily make copies of your files available to other users without checking the changelist into the depot.

Shelving is useful for individual developers who are switching between tasks or performing cross-platform testing before checking in their changes. Shelving also enables teams to easily hand off changes and to perform code reviews.

Example Shelving a changelist

Earl has made changes to `command.c` on a UNIX platform, and now wants others to be able to view and test his changes.

```
$ p4 edit //Acme/dev/command.c
//Acme/dev/command.c#9 - opened for edit
...

$ p4 shelve
Change 123 created with 1 open file(s).
Shelving files for change 123.
edit //Acme/dev/command.c#9
Change 123 files shelved.
```

A pending changelist is created, and the shelved version of `command.c` is stored in the server. The file `command.c` remains editable in Earl's workspace, and Earl can continue to work on the file, or can revert his changes and work on something else.

Shelved files remain open in the changelist from which they were shelved. (To add a file to an existing shelved changelist, you must first open that file in that specific changelist.) You can continue to work on the files in your workspace without affecting the shelved files. Shelved files can be synced to other workspaces, including workspaces owned by other users. For example:

Example Unshelving a changelist for code review

Earl has asked for code review and a cross-platform compatibility check on the version of `command.c` that he shelved in changelist 123. Bruno, who is using a Windows computer, types:

```
C:\bruno_ws\dev> p4 unshelve -s 123 //Acme/dev/command.c
//Acme/dev/command.c#9 - unshelved, opened for edit
```

and conducts the test in the Windows environment while Earl continues on with other work.

When you shelve a file, the version on the shelf is unaffected by commands that you perform in your own workspace, even if you revert the file to work on something else.

Example Handing off files to other users

Earl's version of `command.c` works on UNIX, but Bruno's cross-platform check of `command.c` has revealed a bug. Bruno can take over the work from here, so Earl reverts his workspace and works on something else:

```
$ p4 revert //Acme/dev/command.c
//Acme/dev/command.c#9 - was edit, reverted
```

The shelved version of `command.c` is still available from Earl's pending changelist 123, and Bruno opens it in a new changelist, changelist 124.

```
$ p4 unshelve -s 123 -c 124 //Acme/dev/command.c
//Acme/dev/command.c#9 - unshelved, opened for edit
```

When Bruno is finished with the work, he can either re-shelve the file (in his own changelist 124, not Earl's changelist 123) for further review — with the `p4 reshelve` command — or discard the shelved file and submit the version in his workspace by using `p4 submit`.

The `p4 submit` command has a `-e` option that enables the submitting of shelved files directly from a changelist. All files in the shelved change must be up to date and resolved. Other restrictions can apply in the case of files shelved to stream targets; see the [Helix Core P4 Command Reference](#) for details. (To avoid dealing with these restrictions, you can always move the shelved files into a new pending changelist before submitting that changelist.)

Example Discarding shelved files before submitting a change

The Windows cross-platform changes are complete, and changelist 124 is ready to be submitted. Bruno uses `p4 shelve -d` to discard the shelved files.

```
C:\bruno_ws\dev> p4 shelve -d -c 124
Shelve 124 deleted.
```

All files in the shelved changelist are deleted. Bruno can now submit the changelist.

```
C:\bruno_ws\dev> p4 submit -c 124
Change 124 submitted.
```

Bruno could have shelved the file in changelist 124, and let Earl unshelve it back into his original changelist 123 to complete the check-in.

Display information about changelists

To display brief information about changelists, use the `p4 changes` command. To display full information, use the `p4 describe` command. The following table describes some useful reporting commands and options:

Command	Description
<code>p4 changes</code>	Displays a list of all pending, submitted, and shelved changelists, one line per changelist, and an abbreviated description.
<code>p4 changes -m count</code>	Limits the number of changelists reported on to the last specified number of changelists.
<code>p4 changes -s status</code>	Limits the list to those changelists with a particular status; for example, <code>p4 changes -s submitted</code> lists only already submitted changelists.
<code>p4 changes -u user</code>	Limits the list to those changelists submitted by a particular user.
<code>p4 changes -c workspace</code>	Limits the list to those changelists submitted from a particular client workspace.
<code>p4 describe changenum</code>	Displays full information about a single changelist. If the changelist has already been submitted, the report includes a list of affected files and the diffs of these files. (You can use the <code>-s</code> option to exclude the file diffs.)
<code>p4 describe -O changenum</code>	If a changelist was renumbered, describe the changelist in terms of its original change number. See at " Create numbered changelists " on page 56, where "Example: Automatic renumbering of changelists" shows a case where you can use either <code>p4 describe 783</code> or <code>p4 describe -O 777</code> .

For more information, see "[Changelist reporting](#)" on page 159.

Move files between changelists

Move files between changelists

To move files from one changelist to another, issue the `p4 reopen -c changenumfilenames` command, where *changenumber* specifies the number of the target changelist. If you are moving files to the default changelist, use `p4 reopen -c default filenames`.

Delete changelists

To delete a pending changelist, you must first remove all files and jobs associated with it and then issue the `p4 change -d changenum` command. Related operations include the following:

- To move files to another changelist, issue the `p4 reopen -c changenum` command.
- To remove files from the changelist and discard any changes, issue the `p4 revert -c changenum` command.

Changelists that have already been submitted can be deleted only by a Helix server administrator. See [Deleting changelists and editing changelist descriptions](#) in the Helix Core Server Administrator Guide.

Other recurring tasks

Configure client behavior	60
Configure stream behavior	60
Branch and populate child streams	61
Propagate changes	61

Configure client behavior

You can configure many aspects of the behavior of both the client workspace and the client binary running on your computer.

"Configure clients" on page 63 discusses client configuration in detail.

Configure stream behavior

You can configure a stream's characteristics — such as its location, its type, and the files in its view, among other things.

"Configure a stream" on page 87 discusses stream configuration in detail.

Branch and populate child streams

After populating the mainline — as described in "Populate the mainline stream" on page 45 — you can branch files for development and for release. For example, to create a development stream that is a clone of its mainline parent, issue the following command:

```
$ p4 stream -t development -P //Acme/main //Acme/dev
```

Helix server displays the stream specification with the type set to development. Save the specification. To populate the stream with the files from the mainline, issue the following commands:

```
$ p4 populate -d "From main" -S //Acme/dev -r
$ p4 sync
```

Propagate changes

Streams enable you to isolate stable code from work in progress, and to work concurrently on various projects without impediment. Best practice is to periodically update less stable streams from streams that are more stable (by merging), then promote changes to the more stable stream (by copying). Merging and copying are streamlined forms of integration. In general, propagate change as follows:

- For copying and branching, use `p4 copy` or `p4 populate`.
- For merging, use `p4 merge`.
- For edge cases not addressed by `p4 merge` or `p4 copy`, use `p4 integrate`.

The preceding guidelines apply to classic Helix server as well.

Merge changes from a more stable stream

To update a stream with changes from a more stable stream, issue the `p4 merge -S source-stream` command, resolve as required, and submit the resulting changelist. By default, you cannot copy changes to a more stable stream until you have merged any incoming changes from the intended target. This practice ensures that you do not inadvertently overwrite any of the contents of the more stable stream.

Assuming changes have been checked into the mainline after you started working in the development stream (and assuming your workspace is set to a development stream), you can incorporate the changes into the development stream by issuing the following commands:

```
$ p4 merge
$ p4 resolve
$ p4 submit -d "Merged latest changes"
```

Copy changes to a more stable stream

After merging, your stream is up to date with its more stable parent or child. Assuming you've finalized the changes you want to make in the development stream, you can now promote its new content with no danger of overwriting work in the target stream. The copy operation simply propagates a duplicate of the source to the target, with no resolve required. For example, (and assuming your workspace is set to a mainline parent stream) to promote changes from the development stream to its parent mainline, issue the following commands:

```
$ p4 copy --from //Acme/dev
$ p4 submit -d "Check my new feature in"
```

Compare changes between streams

Using the `p4 interchanges` command, you can compare changes between streams to look for outstanding merges. Suppose you have a mainline stream `//Acme/main` and its child, a development stream, `//Acme/dev`. The following command tells you which changes exist in `//Acme/dev` but not in its parent stream:

```
$ p4 interchanges -S //Acme/dev
```

The following command tells you which changes exist in the parent of `//Acme/dev` but not in `//Acme/dev`:

```
$ p4 interchanges -S -r //Acme/dev
```

Propagate change across the stream hierarchy

You might need to propagate a specific change between two streams that do not have a parent-child relationship in the stream hierarchy. For example, to obtain an in-progress feature or bug fix from a peer development stream. To merge from or copy to such a stream, you can re-parent your stream by editing its specification and setting the `Parent:` field to the desired source or target. This practice is not considered optimal but might be necessary.

Alternatively, you can use the `-P` option with the `p4 merge` command to do a one-off merge of the streams.

Configure clients

You can configure many aspects of the behavior of a command-line client, including which server port it listens on, the current client workspace name, and how files are mapped from the depot to the client workspace.

In Helix server, the word "client" can refer to either:

- The client process — the running client binary ([p4](#))
- The *client workspace* — the location on your computer where you work on file revisions managed by Helix server

This chapter discusses configuring both.

Configure the client process	64
Using the command line	64
Using config files	65
Using environment variables	66
Using the Windows registry or OS X system settings	67
Configure for IPv6 networks	67
Configure for Unicode	68
Configure a client workspace	69
How Helix server manages files in a workspace	70
Define a client workspace	70
Configure workspace options	72
Configure submit options	73
View a stream as of a specific changelist	74
Configure line-ending settings	75
Change the location and/or layout of your workspace	75
Manage workspaces	76
Delete a client workspace	77
Configure workspace views	78
Specify mappings	79
Use wildcards in workspace views	79
Map part of the depot	80
Map files to different locations in the workspace	80
Map files to different filenames	80
Rearrange parts of filenames	81
Exclude files and directories	81
Map a single depot path to multiple locations in a workspace	81
Restrict access by changelist	82
Avoid mapping conflicts	83
Automatically prune empty directories from a workspace	83
Map different depot locations to the same workspace location	83
Deal with spaces in filenames and directories	84
Map Windows workspaces across multiple drives	84
Use the same workspace from different computers	85

Configure the client process

This guide refers to client settings using environment variables. For example, `set P4CLIENT`.

Tip

You can specify settings such as port, user, and workspace names by using any of the following:

1. On the command line, using options.
2. In the configuration file(s) specified by a `P4CONFIG` environment variable, where each config file can be specific to a workspace.
3. In the `P4ENVIRO` configuration file, which is for variables that remain constant for all the workspaces on a given computer.
4. User environment variables.
5. System environment variables (on Windows, system-wide environment variables are not necessarily the same thing as user environment variables)
6. In the user registry or settings set by issuing the `p4 set` command.
7. In the system registry or system settings set by issuing the `p4 set -s` command.

where (1) the command line overrides (2) `P4CONFIG`, and (2) `P4CONFIG` overrides (3) `P4ENVIRO`, and so on.

The output of `p4 set` lists the values of the variables (and if a given variable was set by `config`, `enviro`, `set`, or `set -s`).

To configure your computer to connect to the Helix server, you specify the name of the host where the server is running, and the port on which it is listening. The default host is `perforce` and default port is 1666. If the server is running on your own computer, specify `localhost` as the host name. If the server is running on port 1666, you can omit the port specification.

You can specify these settings as described in the sections below. For details about working offline (without a connection to a Helix server), see "Work offline" on page 127.

Also in this section:

Using the command line	64
Using config files	65
Using environment variables	66
Using the Windows registry or OS X system settings	67
Configure for IPv6 networks	67
Configure for Unicode	68

Using the command line

To specify these settings on the command line, use the `-p` option. For example:

```
$ p4 -p tcp:localhost:1776 sync //JamCode/dev/jam/Jambase
```

Settings specified on the command line override any settings specified in config files, environment variables, the Windows registry, or OS X system settings. For more details about command-line options, refer to the discussion of global options in the [Helix Core P4 Command Reference](#).

Using config files

Config files are text files containing settings that are in effect for files in and below the directory where the config file resides. Config files are useful if you have multiple client workspaces on the same computer. By specifying the settings in config files, you avoid the inconvenience of changing system settings every time you want to work with a different workspace.

To use config files, you define the `P4CONFIG` environment variable, specifying a file name (for example, `.p4config`). When you issue a command, Helix server searches the current working directory and its parent directories for the specified file and uses the settings it contains (unless the settings are overridden by command-line options).

Each setting in the file must be specified on its own line, using the following format:

```
setting=value
```

Note

Make sure there are no spaces. For example, `setting = value` will not work.

The following settings can be specified in a config file:

Setting	Description
<code>P4CHARSET</code>	Character set used for translation of Unicode files.
<code>P4COMMANDCHARSET</code>	Non-UTF-16 or UTF-32 character set used by Command-Line Client when <code>P4CHARSET</code> is set to a UTF-16 or UTF-32 character set.
<code>P4CLIENT</code>	Name of the current client workspace.
<code>P4DIFF</code>	The name and location of the diff program used by <code>p4 resolve</code> and <code>p4 diff</code> .
<code>P4EDITOR</code>	The editor invoked by those Helix server commands that use forms.
<code>P4HOST</code>	Hostname of the client computer. Only useful if the <code>Host:</code> field of the current client workspace has been set in the <code>p4 client</code> form.
<code>P4IGNORE</code>	A list of files to ignore when using the <code>p4 add</code> and <code>p4 reconcile</code> commands.

Setting	Description
P4LANGUAGE	This environment variable is reserved for system integrators.
P4MERGE	The name and location of the third-party merge program to be used by p4 resolve 's merge option.
P4PASSWD	Supplies the current Helix server user's password for any Helix server command.
P4PORT	The protocol, host and port number of the Helix server (including proxies or brokers) with which to communicate.
P4TRUST	The location of a file of known (trusted) Helix server. You manage the contents of this file with the p4 trust command. By default, this file is .p4trust in your home directory.
P4USER	Current Helix server user name.

For details about these settings, refer to the [Helix Core P4 Command Reference](#).

Example Using config files to handle switching between two workspaces

Ona switches between two workspaces on the same computer. The first workspace is **ona-ash**. It has a client root of **/tmp/user/ona** and connects to the Helix server using SSL at **ssl:ida:1818**. The second workspace is called **ona-agave**. Its client root is **/home/ona/p4-ona**, and it uses a plaintext connection to a Helix server at **tcp:warhol:1666**.

Ona sets the **P4CONFIG** environment variable to **.p4settings**. She creates a file called **.p4settings** in **/tmp/user/ona** containing the following text:

```
P4PORT=ssl:ida:1818
P4CLIENT=ona-ash
```

She creates a second **.p4settings** file in **/home/ona/p4-ona**. It contains the following text:

```
P4PORT=tcp:warhol:1666
P4CLIENT=ona-agave
```

Any work she does on files under **/tmp/user/ona** is managed by the Helix server at **ssl:ida:1818** and work she does on files under **/home/ona/p4-ona** is managed by the Helix server at **tcp:warhol:1666**.

Using environment variables

To configure connection settings using environment variables, set **P4PORT** to **protocol:host:port**, as in the following examples:

If the server runs on	and listens to port	supports encryption protocol	set <code>P4PORT</code> to
your computer	1666	nothing (plaintext)	<code>localhost:1666</code>
<code>perforce</code>	1666	SSL	<code>ssl:perforce:1666</code>
<code>houston</code>	3435	nothing (plaintext)	<code>tcp:houston:3435</code>
<code>example.com</code>	1818	SSL	<code>ssl:example.com:1818</code>

If you do not specify a protocol in your `P4PORT` setting, `tcp:` (plaintext communication over TCP/IP) is assumed. If the Helix server has been configured to support SSL, you can encrypt your connection to Helix server by using `ssl:` as the desired protocol.

Other protocols (for example, `tcp4:` to require a plaintext IPv4 connection, or `ssl64:` to require an encrypted connection, but to prefer the use of the IPv6 transport instead of IPv4) are available for use in mixed networking environments.

See "Configure for IPv6 networks" below, and the *Helix Core Server Administrator Guide*, for details.

Using the Windows registry or OS X system settings

On Windows and OS X computers, you can store connection settings in the registry (or system settings) by using the `p4 set` command. For example:

```
$ p4 set P4PORT=ssl:tea.example.com:1667
```

There are two ways you can configure client settings in the registry:

- `p4 set setting=value`: for the current local user.
- `p4 set -s setting=value`: for all users on the local computer. Can be overridden by any registry settings made for the local user. Requires administrative privileges.

To see which settings are in effect, use the `p4 set` command without arguments. For details about the `p4 set` command, see the *Helix Core P4 Command Reference*.

Configure for IPv6 networks

Helix server supports connectivity over IPv6 networks as well as over IPv4 networks.

Depending on the configuration of your LAN or WAN, your system administrator might recommend different port settings. Your administrator might also recommend that you set the `net.rfc3484` configurable to `1`, either from the command line or in a `P4CONFIG` file:

```
$ p4 configure set net.rfc3484=1
```

Doing so ensures RFC3484-compliant behavior if the protocol value is not explicitly specified. For example, if the client-side configurable `net.rfc3484` is set to `1`, and `P4PORT` is set to `example.com:1666`, or `tcp:example.com:1666`, or `ssl:example.com:1666`, the user's operating system automatically determines, for any given connection, whether to use IPv4 or IPv6 when communicating with the versioning server.

For more information, see [IPv6 support and mixed networks](#) in the *Helix Core Server Administrator Guide* and [P4PORT](#) in *Helix Core P4 Command Reference*.

Configure for Unicode

The Helix server can be run in Unicode mode to activate support for file names or directory names that contain Unicode characters, and Helix server identifiers (for example, user names) and specifications (for example, changelist descriptions or jobs) that contain Unicode characters.

In Unicode mode, the Helix server also translates Unicode files and metadata to the character set configured on the user's computer, and verifies that the Unicode files and metadata contain valid UTF-8 characters.

Note

If you only need to manage textual files that contain Unicode characters, but do not need the features listed under "Configure for Unicode" above, you do not need to run Helix server in Unicode mode. Your system administrator will tell you if your site is using Unicode mode or not. For these installations, assign the Helix server `utf16` file type to textual files that contain Unicode characters. You do not have to set the `P4CHARSET` or `P4COMMANDCHARSET` environment variables. See "Assigning file types for Unicode files" on page 170 for details.

To correctly inter-operate in Unicode mode, and to ensure that such files are translated correctly by the Helix server when the files are synced or submitted, you must set `P4CHARSET` to the character set that corresponds to the format used on your computer by the applications that access them, such as text editors or IDEs. These formats are typically listed when you save the file using the **Save As...** menu option.

Values of `P4CHARSET` that begin with `utf16` or `utf32` further require that you also set `P4COMMANDCHARSET` to a non `utf16` or `utf32` character set in which you want server output displayed. "Server output" includes informational and error messages, diff output, and information returned by reporting commands.

For a complete list of valid `P4CHARSET` values, issue the command `p4 help charset`.

For further information, see the *Helix Core Server Administrator Guide*.

Setting P4CHARSET on Windows

To set `P4CHARSET` for all users on a computer, you need Windows administrator privileges. Issue the following command:

```
C:\bruno_ws> p4 set -s P4CHARSET=character_set
```

To set `P4CHARSET` for the user currently logged in:

```
c:\bruno_ws> p4 set P4CHARSET=character_set
```

Your computer must have a compatible TrueType or OpenType font installed.

Setting P4CHARSET on UNIX

You can set **P4CHARSET** from a command shell or in a startup script such as **.kshrc**, **.cshrc**, or **.profile**. To determine the proper value for **P4CHARSET**, examine the setting of the **LANG** or **LOCALE** environment variable. Common settings are as follows

If LANG is...	Set P4CHARSET to
en_US.ISO_8859-1	iso8859-1
ja_JP.EUC	eucjp
ja_JP.PCK	shiftjis

In general, for a Japanese installation, set **P4CHARSET** to **eucjp**, and for a European installation, set **P4CHARSET** to **iso8859-1**.

Configure a client workspace

A Helix server *client workspace* is a set of directories on your computer where you work on file revisions that are managed by Helix server. Each workspace is given a name that identifies the client workspace to the Helix server. If no workspace name is specified (by setting the **P4CLIENT** environment variable) the default workspace name is the name of your computer. To specify the effective workspace name, set the **P4CLIENT** environment variable. You can have multiple workspaces on your computer.

All files within a Helix server client workspace share a root directory, called the *client workspace root*. The workspace root is the highest-level directory of the workspace under which the managed source files reside.

If you configure multiple workspaces on the same computer, keep workspace locations separate to avoid inadvertently overwriting files. Ensure that client roots are located in different folders and that their workspace views do not map depot files to overlapping locations on your computer.

Although Windows-based systems do not have a root directory, Helix server supports — via the concept of a null root — workspaces spread across multiple drives and/or a disjoint folder with only **c:** as the root.

Also in this section:

How Helix server manages files in a workspace	70
Define a client workspace	70
Configure workspace options	72

Configure submit options	73
View a stream as of a specific changelist	74
Configure line-ending settings	75
Change the location and/or layout of your workspace	75
Manage workspaces	76
Delete a client workspace	77

How Helix server manages files in a workspace

Helix server manages the files in a client workspace as follows:

- Files in the workspace are created, updated, and deleted as determined by your changes.
- Write permission is enabled when you edit a file, and disabled when you submit your changes.

The state of your workspace is tracked and managed by Helix server. To avoid conflicts with the file management performed by Helix server applications, do not manually change read-only permission settings on files. Helix server has commands that help you determine whether or not the state of your client workspace corresponds to Helix server's record of that state; see ["Work offline" on page 127](#) for details.

Files in the workspace that you have not put under Helix server control are ignored by Helix server. For example, compiled objects, libraries, executables, and developers' temporary files that are created while developing software but not added to the depot are not affected by Helix server commands.

By default, when you create a client workspace, the entire depot is mapped to your workspace. You can refine this mapping to view only a portion of the depot and to change the correspondence between depot and workspace locations, by refining the *workspace view*, as described in ["Configure workspace views" on page 78](#).

Define a client workspace

The following procedure explains how to define a client workspace. Note that no files are synced when you create a client specification. To find out how to sync files from the depot to your workspace, see ["Sync files" on page 48](#). For details about relocating files on your computer, see ["Change the location and/or layout of your workspace" on page 75](#).

Tip

The client storage type cannot be changed after the client workspace is created. For example, a **readonly** client cannot be changed into a **writable** client.

To define a client workspace:

1. Specify the workspace name by setting `P4CLIENT`; for example, on a UNIX system:

```
$ export P4CLIENT=bruno_ws
```

2. Issue the `p4 client` command.

Important

Stream users must pass in the `S_streamname` option to the `p4 client` command to specify the name of the stream to which Helix server should bind the workspace.

Helix server displays the client specification form in your text editor. (For details about Helix server forms, see ["Using Helix server forms" on page 184.](#))

3. Specify (at least the minimum) settings and save the specification.

The minimum settings you must specify to configure a client workspace are:

- **Workspace name**

The workspace name defaults to your computer's hostname, but your computer can contain multiple workspaces. To specify the effective workspace, set `P4CLIENT`.

- **Workspace root**

The client workspace root is the top directory of your client workspace, where Helix server stores your working copies of depot files. Be sure to set the workspace root, or you might inadvertently sync files to your computer's root directory.

Note

For Windows users: when specifying a workspace root, you must include the drive letter. In addition, root is null on Windows when the client workspace is either on a disjoint drive with only `c:\` as the root and/or is spread over multiple drives.

If the workspace root directory does not exist, you must create it before the Helix server application can make use of it.

The `@`, `#`, `*`, and `%` characters have specific meaning to Helix server; if you have file or folder names that use these characters, see ["Restrictions on filenames and identifiers" on page 179](#) for details.

- **Workspace view**

By default, the entire depot is mapped to your workspace. You can define a *workspace view* (also referred to as a *client view*) to determine which files in the depot are mapped to your workspace. This enables Helix server to construct a one-to-one mapping between individual depot and workspace files. You can map files to have different names and locations in your workspace than they have in the depot.

For users of streams, Helix server *generates* the workspace view from the contents of the stream spec's `Paths:` field. Users of classic Helix server branches configure the workspace view by editing the contents of the client spec's `View:` field.

For details on configuration of workspace views, see ["Configure workspace views" on page 78](#).

Configure workspace options

The following table describes the client spec `Options`: in detail:

Option	Description	Default
<code>[no]allwrite</code>	<p>Specifies whether unopened files are always writable. By default, Helix server makes unopened files read-only. To avoid inadvertently overwriting changes or causing syncs to fail, specify <code>noallwrite</code>.</p> <p>A setting of <code>allwrite</code> leaves unopened files writable by the current user; it does not set filesystem permissions to ensure that files are writable by any user of a multiuser system.</p> <p>If <code>allwrite</code> and <code>noclobber</code> are both set, Helix server performs a safe sync, comparing the content in your client workspace against what was last synced. If the file was modified outside of Helix server control, an error message is displayed and the file is not overwritten.</p>	<code>noallwrite</code>
<code>[no]clobber</code>	<p>Specifies whether <code>p4 sync</code> overwrites writable but unopened workspace files. (By default, Helix server does not overwrite unopened files if they are writable.)</p> <p>If <code>allwrite</code> and <code>noclobber</code> are both set, Helix server performs a safe sync, comparing the content in your client workspace against what was last synced. If the file was modified outside of Helix server control, an error message is displayed and the file is not overwritten.</p>	<code>noclobber</code>
<code>[no]compress</code>	<p>Specifies whether data is compressed when it is sent between your computer and the Helix server.</p>	<code>nocompress</code>

Option	Description	Default
<code>[un]locked</code>	Specifies whether other users can use, edit, or delete the client workspace specification. A Helix server administrator can override the lock with the <code>-f</code> (force) option. If you lock your client specification, be sure to set a password for the workspace's owner using the <code>p4 passwd</code> command.	<code>unlocked</code>
<code>[no]modtime</code>	For files <i>without</i> the <code>+m</code> (modtime) file type modifier, if <code>modtime</code> is set, the modification date (on the local filesystem) of a newly synced file is the timestamp <i>on the file</i> when the file was submitted to the depot. If <code>nomodtime</code> is set, the modification date is the date and time of sync. For files <i>with</i> the <code>+m</code> (modtime) file type, the modification date (on the local filesystem) of a newly synced file is the timestamp on the file when the file was submitted to the depot, regardless of the setting of <code>modtime</code> or <code>nomodtime</code> on the client.	<code>nomodtime</code> (date and time of sync). Ignored for files with the <code>+m</code> file type modifier.
<code>[no]rmdir</code>	Specifies whether <code>p4 sync</code> deletes empty directories in a workspace if all files in the directory have been removed.	<code>normdir</code>

Configure submit options

To control what happens to files in a changelist when you submit the changelist to the depot, set the `SubmitOptions:` field. Valid settings are as follows.

Option	Description
<code>submitunchanged</code>	All open files (with or without changes) are submitted to the depot. This is the default behavior of Helix server.
<code>submitunchanged+reopen</code>	All open files (with or without changes) are submitted to the depot, and all files are automatically reopened in the default changelist.
<code>revertunchanged</code>	Only those files with content, type, or resolved changes are submitted to the depot. Unchanged files are reverted.

Option	Description
<code>revertunchanged+reopen</code>	Only those files with content, type, or resolved changes are submitted to the depot and reopened in the default changelist. Unchanged files are reverted and <i>not</i> reopened in the default changelist.
<code>leaveunchanged</code>	Only those files with content, type, or resolved changes are submitted to the depot. Any unchanged files are moved to the default changelist.
<code>leaveunchanged+reopen</code>	Only those files with content, type, or resolved changes are submitted to the depot. Unchanged files are moved to the default changelist, and changed files are reopened in the default changelist. This option is similar to <code>submitunchanged+reopen</code> , except that no unchanged files are submitted to the depot.

View a stream as of a specific changelist

The `StreamAtChange` option in the client spec lets you use the version of the stream specified as of a particular changelist to generate a workspace view. This is helpful when you want to see what the stream view was at a particular point in time, especially if your stream spec changes a lot (for example, if you frequently change what you're importing or what you're deciding to share). When you use the `StreamAtChange` option, you cannot submit changes to the files in the stream, since your workspace view is not up to date.

To set a stream workspace to use the version of the stream specified as of a particular changelist, do the following:

1. Open the stream's workspace specification form for editing.

```
$ p4 client
```

2. Use one of the following alternatives:

- a. Edit the form to set `StreamAtChange` to the changelist you want to view the stream as of. Or,
- b. Issue this command:

```
$ p4 client -S //Ace/main@12546
```

For more information, see the [Helix Core P4 Command Reference](#).

Alternatively, you can issue the following command to sync a stream using the stream's view as of a specific changelist:

```
$ p4 switch [-r -v] stream@change
```

This command both sets the `StreamAtChange` value and syncs to the same change.

Configure line-ending settings

To specify how line endings are handled when you sync text files, set the **LineEnd:** field. Valid settings are as follows:

Option	Description
local	Use mode native to the client (default)
unix	UNIX-style (and Mac OS X) line endings: LF
mac	Mac pre-OS X: CR only
win	Windows- style: CR , LF
share	<p>The share option normalizes mixed line-endings into UNIX line-end format. The share option does not affect files that are synced into a client workspace; however, when files are submitted back to the Helix server server, the share option converts all Windows-style CR/LF line-endings and all Mac-style CR line-endings to the UNIX-style LF, leaving lone <code>`LF`</code>s untouched.</p> <p>When you sync your client workspace, line endings are set to LF. If you edit the file on a Windows computer, and your editor inserts CR's before each LF, the extra CR's do not appear in the archive file.</p> <p>The most common use of the share option is for users of Windows computers who mount their UNIX home directories as network drives; if you sync files from UNIX, but edit the files on a Windows computer.</p> <p>The share option implicitly edits the file(s) during a submit. As a consequence, if you have set the LineEnd field to share in your client spec, the p4 resolve command may prompt you to edit the file before resolving.</p>

For detailed information about how Helix server uses the line-ending settings, see the Support Knowledgebase article, "[CR/LF Issues and Text Line-endings](#)".

Change the location and/or layout of your workspace

To change the location of files in your workspace, issue the **p4 client** command and change either or both of the **Root:** and **View:** fields. Before changing these settings, ensure that you have no files checked out (by submitting or reverting open files).

If you're using streams, you must change the **Paths:** field in the stream spec, rather than the **View:** field, in the client spec.

If you intend to modify both fields, perform the following steps to ensure that your workspace files are located correctly:

1. To remove the files from their old location in the workspace, issue the `p4 sync ...#none` command.
2. Change the `Root:` field. (The new client workspace root directory must exist on your computer before you can retrieve files into it.)
3. To copy the files to their new locations in the workspace, perform a `p4 sync`. (If you forget to perform the `p4 sync ...#none` before you change the workspace view, you can always remove the files from their client workspace locations manually).
4. Users of streams, change the `Paths:` field in the stream spec. Users of classic Helix server branches, change the `View:` field in the client spec.
5. Again, perform a `p4 sync`. This time, syncing changes the layout of the workspace. The files in the client workspace are synced to their new locations.

Manage workspaces

This section discusses various approaches to managing your stream workspaces.

Using one workspace for multiple streams

When working with multiple streams, you have two choices:

- Switch one workspace between multiple streams; the workspace is appropriately populated whenever you switch from one stream to another. While this requires some extra processing, it is the right choice when you don't need to work on different streams at the same time and you don't want to have multiple streams on disk at the same time.
- Establish a distinct workspace for each stream. This is the right choice if you want to move quickly between different streams or if you want to have multiple streams on disk at the same time.

Note that distinct workspaces must have distinct workspace roots — that is, distinct local folders.

To change the stream associated with a workspace, issue the following command:

```
$ p4 switch streamname
```

To get a workspace view and a set of files as of a specific changelist, issue the following command:

```
$ p4 switch stream@change
```

Narrowing the scope of workspaces with virtual streams

For large projects, even consistently-organized streams may not sufficiently restrict workspace views. In large organizations, there are often many groups who are concerned with only a small subset of a project's files. In classic Helix server, these users would manually restrict their workspace's view to include only the desired subset. Streams offer an analog; use a virtual stream as a filter:

For example, if ongoing development work is occurring in an `//Ace/dev` stream:

```
Stream:    //Ace/dev
Parent:    //Ace/main
Type:      development
Paths:
    share ...
```

Then a user who is working only with the documentation for the product (rather than all of the assets associated with the project) could create a virtual stream that includes only those files under `//Ace/dev/docs/...`, as follows:

```
Stream:    //Ace/devdocs
Parent:    //Ace/dev
Type:      virtual
Paths:
    share docs/...
```

The user can then switch his or her workspace to the `devdocs` virtual stream with the following command:

```
$ p4 switch //Ace/devdocs
```

When using the `devdocs` workspace, the user's workspace view is automatically updated to include only the material in `//Ace/dev/docs/...` and any changes he or she makes in `//Ace/devdocs` are automatically made directly in the original `//Ace/dev` codeline without the need to manually run `p4 copy` or `p4 merge`.

For details on virtual streams, see ["Virtual streams" on page 93](#).

Delete a client workspace

To delete a workspace, issue the `p4 client -d clientname` command. Deleting a client workspace removes Helix server's record of the workspace but does not remove files from the workspace or the depot.

When you delete a workspace specification:

1. Revert (or submit) any pending or shelved changelists associated with the workspace.
2. Delete existing files from a client workspace (`p4 sync ... #none`). (optional)
3. Delete the client spec.

If you delete the client spec before you delete files in the workspace, you can delete workspace files using your operating system's file deletion command.

Configure workspace views

By default, when you create a client workspace, the entire depot is mapped to your workspace. You can refine this mapping to view only a portion of the depot and to change the correspondence between depot and workspace locations.

Helix server generates workspace views automatically from the stream spec for all workspaces bound to that stream. When you bind a workspace to a stream, Helix server generates the workspace view based on the depot mapping entries in the stream spec's **Paths:** field. If the structure of the stream changes, Helix server updates the views of workspaces associated with the stream on an as-needed basis.

For details on all stream spec fields, see ["Configure a stream" on page 87](#).

Note

Non-stream users can update the client workspace view by

1. Invoking the `p4 client` command, which opens the client spec.
2. Editing the **View:** field in the client spec.

However, a user with a stream client cannot change the client view by invoking the `p4 client` command. To change the client view, the stream spec **Paths:** field would need to be changed. However, such a change would affect all clients in that stream.

See also ["Private editing of streams" in p4 stream](#).

To modify a workspace view, issue the `p4 stream` command. Helix server displays the stream specification form, which lists mappings in the **Paths:** field.

Suppose your stream spec contains the following entries under **Paths:**:

```
Paths:
import ...
isolate apps/bin/...
share apps/xp/...
exclude tests/...
```

Switching your workspace to this stream gives you this workspace view:

```
//Acme/XProd/apps/bin/... //bruno_ws/apps/bin/...
//Acme/XProd/apps/xp/... //bruno_ws/apps/xp/...
-//Acme/XProd/tests/... //bruno_ws/tests/...
```

The sections below provide details about specifying the workspace view. For more information, see the description of views in the [Helix Core P4 Command Reference](#).

Specify mappings

Views consist of multiple *mappings*. Each mapping has two parts.

- The left-hand side specifies one or more files in the depot and has the form:
`//depotname/file_specification`
- The right-hand side specifies one or more files in the client workspace and has the form:
`//clientname/file_specification`

The left-hand side of a workspace view mapping is called the *depot side*, and the right-hand side is the *client side*.

To determine the location of any workspace file on your computer, substitute the client workspace root for the workspace name on the client side of the mapping. For example, if the workspace root is `C:\bruno_ws`, the file `//JamCode/dev/jam/Jamfile` resides in `C:\bruno_ws\dev\jam\Jamfile`.

Later mappings override earlier ones. In the example below, the second line overrides the first line, mapping the files in `//Acme/dev/docs/manuals/` up two levels. When files in `//Acme/dev/docs/manuals/` are synced, they reside in `c:\bruno_ws\docs\`.

View:

```
//Acme/dev/...           //bruno_ws/dev/...
//Acme/dev/docs/...     //bruno_ws/docs/...
```

Use wildcards in workspace views

To map groups of files in workspace views, you use Helix server wildcards. Any wildcard used on the depot side of a mapping must be matched with an identical wildcard in the mapping's client side. You can use the following wildcards to specify mappings in your client workspace:

Wildcard	Description
*	Matches anything except slashes. Matches only within a single directory. Case sensitivity depends on your platform.
...	Matches anything including slashes. Matches recursively (everything in and below the specified directory).
%%1 - %%9	Positional specifiers for substring rearrangement in filenames.

In the following simple workspace view, all files in the depot's `dev` stream are mapped to the corresponding locations in the client workspace:

```
//JamCode/dev/... //bruno_ws/dev/...
```

For example, the file `//JamCode/dev/jam/Makefile` is mapped to the workspace file `C:\bruno_ws\dev\jam\Makefile`.

Note

To avoid mapping unwanted files, always precede the `...` wildcard with a forward slash.

The mappings in workspace views always refer to the locations of files and directories in the depot; you cannot refer to specific revisions of a file in a workspace view.

Map part of the depot

If you are interested only in a subset of the depot files, map that portion. Reducing the scope of the workspace view also ensures that your commands do not inadvertently affect the entire depot. To restrict the workspace view, change the left-hand side of the **View:** field to specify the relevant portion of the depot.

Example Mapping part of the depot to the client workspace

Dai is working on the Jam project and maintaining the web site, so she sets the **View:** field as follows:

View:

```
//JamCode/dev/jam/...      //dai-beos-locust/jam/...
//JamCode/www/live/...    //dai-beos-locust/www/live/...
```

Map files to different locations in the workspace

Views can consist of multiple mappings, which are used to map portions of the depot file tree to different parts of the workspace file tree. If there is a conflict in the mappings, later mappings have precedence over the earlier ones.

Example Multiple mappings in a single workspace view

The following view ensures that Microsoft Word files in the manuals folder reside in the workspace in a top-level folder called **wordfiles**:

View:

```
//depot/...                //bruno_ws/...
//Acme/dev/docs/manuals/*.doc  //bruno_ws/wordfiles/*.doc
```

Map files to different filenames

Mappings can be used to make the filenames in the workspace differ from those in the depot.

Example Files with different names in the depot and the workspace

The following view maps the depot file `RELNOTES` to the workspace file `rnotes.txt`:

View:

```
//depot/... //bruno_ws/...
//JamCode/dev/jam/RELNOTES //bruno_ws/dev/jam/rnotes.txt
```

Rearrange parts of filenames

Positional specifiers `%%0` through `%%9` can be used to rearrange portions of filenames and directories.

Example Using positional specifiers to rearrange filenames and directories

The following view maps the depot file `//depot/allfiles/readme.txt` to the workspace file `filesbytype/txt/readme`:

View:

```
//depot/allfiles/%%1.%%2 //bruno_ws/filesbytype/%%2/%%1
```

Exclude files and directories

Exclusionary mappings enable you to explicitly exclude files and directories from a workspace. To exclude a file or directory, precede the mapping with a minus sign (`-`). White space is not allowed between the minus sign and the mapping.

Example Using views to exclude files from a client workspace

Earl, who is working on the Jam project, does not want any HTML files synced to his workspace. His workspace view looks like this:

View:

```
//JamCode/dev/jam/... //earl-dev-beech/jam/...
-//JamCode/dev/jam/...html //earl-dev-beech/jam/...html
```

Map a single depot path to multiple locations in a workspace

Helix server includes a "one-to-many" mapping feature, with which you can map a single depot path to multiple locations in a client workspace.

Important

This feature is currently only available for users of classic Helix server branches.

One-to-many mapping is *not* available for streams.

Consider the following scenario: A company has a website whose content is divided into categories such as products, documentation, and technical support. The content for each of these categories is managed in its own location in the workspace.

However, all of these websites display the same logo. Consequently, all three of the locations in the workspace must contain the same image file for the logo.

You might try to map the depot path like this:

View:

```
//Acme/images/logo.png //bruno_ws/products/images/logo.png
//Acme/images/logo.png //bruno_ws/documentation/images/logo.png
//Acme/images/logo.png //bruno_ws/support/images/logo.png
```

When you sync the client, the depot file will only be mapped to the **support** location in the workspace. By default, in a situation in which a workspace view attempts to map a depot path to multiple locations in a client, only the last location is mapped.

To enable the one-to-many mapping feature, prepend **&** to the mapping line for each additional client location you want to map to:

View:

```
//Acme/images/logo.png //bruno_ws/products/images/logo.png
&//Acme/images/logo.png //bruno_ws/documentation/images/logo.png
&//Acme/images/logo.png //bruno_ws/support/images/logo.png
```

When you sync the client, the depot file maps to all three locations.

Important

Mapping lines prepended with **&** are read-only, so in the example above `//bruno_ws/documentation/logo.png` and `//bruno_ws/support/logo.png` are read only.

Restrict access by changelist

You can restrict access to depot paths to a particular point in time by providing the depot path names and changelist numbers in the **ChangeView** field of the client specification. Files specified for the **ChangeView** field are read-only: they can be opened but not submitted. For example:

ChangeView:

```
//depot/path/...@1000
```

In this example, revisions of the files in `//depot/path/...` are not visible if they were submitted after changelist 1000. Files submitted up to and including changelist 1000 are visible but read-only. You can specify multiple paths.

You may specify `ChangeView` entries in either depot syntax or client syntax.

Avoid mapping conflicts

When you use multiple mappings in a single view, a single file can inadvertently be mapped to two different places in the depot or workspace. When two mappings conflict in this way, the later mapping overrides the earlier mapping.

Example Erroneous mappings that conflict

Joe has constructed a view as follows:

```
View:
  //Acme/proj1/...    //joe/project/...
  //Acme/proj2/...    //joe/project/...
```

The second mapping `//Acme/proj2/...` maps to `//joe/project` and conflicts with the first mapping. Because these mappings conflict, the first mapping is ignored; no files in `//Acme/proj1` are mapped into the workspace: `//Acme/proj1/file.c` is not mapped, even if `//Acme/proj2/file.c` does not exist.

Automatically prune empty directories from a workspace

By default, Helix server does not remove empty directories from your workspace. To change this behavior, issue the `p4 client` command and in the `Options:` field, change the option `normdir` to `rmdir`.

For more about changing workspace options, see "Configure workspace options" on page 72.

Map different depot locations to the same workspace location

Overlay mappings enable you to map files from more than one depot directory to the same place in a workspace. To overlay the contents of a second directory in your workspace, use a plus sign (+) in front of the mapping.

Example Overlaying multiple directories in the same workspace

Joe wants to combine the files from his projects when they are synced to his workspace, so he has constructed a view as follows:

```
View:
  //Acme/proj1/...    //joe/project/...
  +//Acme/proj2/...    //joe/project/...
```

The overlay mapping `//Acme/proj2/...` maps to `//joe/project`, and overlays the first mapping. Overlay mappings do not conflict. Files (even deleted files) in `//Acme/proj2` take precedence over files in `//Acme/proj1`. If `//Acme/proj2/file.c` is missing (as opposed to being present, but deleted), then `//Acme/proj1/file.c` is mapped into the workspace instead.

Overlay mappings are useful for applying sparse patches in build environments.

Deal with spaces in filenames and directories

Use quotation marks to enclose files or directories that contain spaces.

Example Dealing with spaces in filenames and directories

Joe wants to map files in the depot into his workspace, but some of the paths contain spaces:

View:

```
//Acme/Release 2.0/... //joe/current/...
//Acme/Release 1.1/... "//joe/Patch Release/..."
//Acme/webstats/2011/... "//joe/2011 Web Stats/..."
```

By placing quotation marks around the path components on the server side, client side, or both sides of the mappings, Joe can specify file names and/or directory components that contain spaces.

For more information, see ["Restrictions on filenames and identifiers" on page 179](#).

Map Windows workspaces across multiple drives

To specify a workspace that spans multiple Windows drives, use a `Root:` of `null` and specify the drive letters (in lowercase) in the workspace view. For example:

```
Client:      bruno_ws
Update:     2011/11/29 09:46:53
Access:     2011/03/02 10:28:40
Owner:      bruno
Root:       null
Options:    noallwrite noclobber nocompress unlocked nomodtime normdir
SubmitOptions: submitunchanged
LineEnd:    local
View:
  //Acme/dev/...      "//bruno_ws/c:/Current Release/..."
```

```
//Acme/release/...  "//bruno_ws/d:/Prior Releases/..."
//Acme/www/...     //bruno_ws/d:/website/...
```

Use the same workspace from different computers

By default, you can only use a workspace on the computer that is specified by the **Host:** field. If you want to use the same workspace on multiple computers with different platforms, delete the **Host:** entry and set the **AltRoots:** field in the client specification. You can specify a maximum of two alternate workspace roots. The locations must be visible from all computers that will be using them, for example through NFS or Samba mounts.

Helix server compares the current working directory against the main **Root:** first, and then against the two **AltRoots:** if specified. The first root to match the current working directory is used. If no roots match, the main root is used.

Note

If you are using a Windows directory in any of your workspace roots, specify the Windows directory as your main client **Root:** and specify your other workspace root directories in the **AltRoots:** field.

In the example below, if user **bruno**'s current working directory is located under **/usr/bruno**, Helix server uses the UNIX path as his workspace root, rather than **c:\bruno_ws**. This approach allows **bruno** to use the same client specification for both UNIX and Windows development.

```
Client: bruno_ws
Owner:  bruno
Description:
    Created by bruno.
Root:   c:\bruno_ws
AltRoots:
    /usr/bruno/
```

To find out which client workspace root is in effect, issue the **p4 info** command and check the **Client root:** field.

If you edit text files in the same workspace from different platforms, ensure that the editors and settings you use preserve the line endings. For details about line-endings in cross-platform settings, see ["Configure line-ending settings" on page 75](#).

Streams

This chapter describes how to configure streams, how to propagate changes between them, and how to update them.

About streams

Streams are like branches, but with additional intelligence built in.

Streams:

- provide clues of where and how to do branching and merging
- guide merging and branching actions that support stability and innovation
- are ideal for implementing the mainline branching model, in which less stable streams merge changes to keep up to date with their parents, then copy work to the parent when the work is stable enough to promote.
- eliminate much of the work needed to define branches, create workspaces, and manage merges
- enable the system to generate views for associated workspaces, eliminating the need for you to update views manually to reflect changes to your stream structure.

When you create a stream, you specify its type, information about the files it is associated with, its relationship to other streams, and how files are to be treated for branching and merging. The system uses the information you provide to encourage merging best practices and to track parallel development.

The stream type tells the system how stable the stream is relative to other streams.

The stream's path information tells the system:

- which files to populate the workspace with
- which files child streams are allowed to branch
- which changelist to lock the files at.

Parent labeling specifies how the stream relates to other streams in the system, helping to determine how change flows through the system.

Note

If you are using Helix server branches and want to use streams instead, see the Support Knowledgebase article, "[Migrating from Classic to Stream Depot](#)".

Configure a stream

To configure a stream, you edit its associated *stream spec*. A stream spec names a path in a stream depot to be treated as a stream. A spec defines the stream's location, its type, its parent stream, the files in its view, whether it inherits its parent stream's view, and other configurable behaviors. You create a stream with the `p4 stream` command.

Note

Files can be *imported* from the parent stream or from other streams in the system.

You can update the entries in a stream spec to change the stream's characteristics. See ["Update streams" on page 106](#)

The following is a sample stream spec:

```
$ p4 stream -o //Acme/dev
# A Perforce Stream Specification.
#
# Use '*p4 help stream*' to see more about stream specifications and
command.

Stream: //Acme/dev

Update: 2020/11/06 10:57:04

Access: 2020/11/06 10:57:04

Owner: bruno

Name: //Acme/dev

Parent: //Acme/main

Type: development

Description:
    Our primary development stream for the project.

Options: allsubmit unlocked toparent fromparent mergeany
```

```

ParentView: inherit

Paths:
    share ...
    import boost/... //3rd_
party/boost/1.53.0/artifacts/original/...
    import boost/lib/linux26x86_64/... //3rd_
party/boost/1.53.0/artifacts/original/lib/linuxx86_64/gcc44libc212/...
    import boost/lib/linux26x86/... //3rd_
party/boost/1.53.0/artifacts/original/lib/linuxx86/gcc44libc212/...
    import protobuf/... //3rd_
party/protobuf/2.4.1/artifacts/patch-1/...
    import gtest/... //3rd_
party/gtest/1.7.0/artifacts/original/...
    import icu/... //3rd_party/icu/53.1/artifacts/original/...
    import p4-bin/lib.ntx64/vs11/p4api_vs2012_dyn.zip
//builds/p15.1/p4-bin/bin.ntx64/p4api_vs2012_dyn.zip
    import p4/... //depot/p15.1/p4/...
    exclude p4/lbr/...
    exclude p4/server/...

Remapped:
    p4/doc/... p4/relnotes/...

Ignored:
    .../~tmp.txt

```

For a description of each field in the stream spec, see "Form Fields" in the [p4 stream](#) topic of *Helix Core P4 Command Reference*.

Also in this section:

Stream types


You assign stream types in a stream hierarchy according to the stream's expected usage, stability, and flow of change:

Type	Description
Development	<ul style="list-style-type: none"> code that changes frequently experiment without destabilizing the mainline stream
Mainline	<ul style="list-style-type: none"> code that changes somewhat frequently, but is more stable than code in development streams it is common to implement new features in the mainline.
Release	<ul style="list-style-type: none"> the most stable code and the closest to being released enable you to put existing features in the final state
Task	<ul style="list-style-type: none"> lightweight short-lived streams see "Task streams" on the facing page
Virtual	<ul style="list-style-type: none"> filtered view of a stream see "Virtual streams" on page 93

Merge down, copy up

A **release** stream is more stable than its **mainline** stream parent.

A **development** stream is less stable than its **mainline** stream parent.



Merging incorporates another stream's changes into your stream, and can require you to resolve conflicts.

Copying duplicates the source stream to the target. Changes are merged down (to streams of lesser stability) and copied up (to streams of greater stability).

Stream types - most stable to least stable

Stream Type	Stability	Merge	Copy
<code>release</code>	Highly stable	to parent	from parent
<code>mainline</code>	Stable per your policy (for example, all code builds)	from child (from release, or to development)	to child (to release, or from development)
<code>development</code>	Unstable	from parent	to parent
<code>task</code>	Unstable	from parent	to parent
<code>virtual</code>	N/A; used to filter streams	N/A	N/A

Also in this section:

Task streams

Task streams are lightweight short-lived streams used for bug fixing or new features that only modify a small subset of the stream data. Since branched (copied) files are tracked in a set of shadow tables that are later removed, repository metadata is kept to a minimum when using this type of stream and server performance is optimized.

They are branches that work just like development streams, but task streams remain semi-private until branched back to the parent stream. Designed as lightweight branches, they are most effective when anticipated work in the branch will only affect a small number of files relative to the number of files in the branch.

Note

DVCS does not support task streams.

Task streams are intended to be deleted or unloaded after use. Because you cannot re-use task stream names even after the stream has been deleted, most sites adopt a naming convention that is likely to be unique for each task, such as *user-date-jobnumber*.

Workflow example

Working within task streams is similar to working in a development stream. The following is an example of a typical workflow.

Suppose that we have an existing stream depot named `Ace` and a defined development stream named `//Ace/dev`.

With the workspace associated with the development stream, we create a task stream and then use `p4 populate` to populate it from the development stream.

```
$ p4 stream -t task -P //Ace/dev //Ace/fixbug1
$ p4 populate -r -S //Ace/fixbug1
2 files branched (change 818).
```

Only a workspace that is associated with a task stream can see the full branch in the task stream. The stream appears as a sparse branch to other workspaces, which see only those files and revisions that you changed within the task stream. Most other metadata for the task stream remains private. Because the workspace is still associated with the development stream, we don't see any files in the newly created task stream:

```
$ p4 files //Ace/fixbug1/...
//Ace/fixbug1/... - no such file(s).
```

Therefore, we associate the workspace with the task stream, and then we see the full branch in the task stream:

```
$ p4 client -s -S //Ace/fixbug1
$ p4 files //Ace/fixbug1/...
//Ace/fixbug1/src.cpp#1 - branch change 818 (text)
//Ace/fixbug1/src.h#1 - branch change 818 (text)
```

We now start work in the task stream and submit content changes:

```
$ p4 add //Ace/fixbug1/foo
//Ace/fixbug1/foo#1 - opened for add
$ p4 submit -d "Add new file to task stream"
$ p4 sync //Ace/fixbug1/src.cpp
$ p4 edit //Ace/fixbug1/src.cpp
//Ace/fixbug1/src.cpp#1 - opened for edit
$ p4 submit -d 'Update to src.cpp in task stream'
```

We see any changes:

```
$ p4 files //Ace/fixbug1/...
//Ace/fixbug1/foo#1 - add change 819 (text)
//Ace/fixbug1/src.cpp#2 - edit change 820 (text)
//Ace/fixbug1/src.h#1 - branch change 818 (text)
```

Content changes in a task stream are promoted when the file action is not a branch or copy. We now associate the workspace with the development stream, and we see that the changes have been promoted from the task stream:

```
$ p4 client -s -S //Ace/dev
$ p4 files //Ace/fixbug1/...
//Ace/fixbug1/foo#1 - add change 819 (text)
//Ace/fixbug1/src.cpp#2 - edit change 820 (text)
```

Before we copy changes from the task stream to the development stream, we merge down any changes from the development stream:

```
$ p4 client -s -S //Ace/fixbug1
$ p4 sync -q
$ p4 merge //Ace/dev/... //Ace/fixbug1/...
//Ace/fixbug1/src.cpp#2 - integrate from //Ace/dev/src.cpp#2
$ p4 resolve -am
$ p4 submit -d 'Merging from dev branch'
```

Now we copy up changes from the task stream:

```
$ p4 client -s -S //Ace/dev
$ p4 sync -q
$ p4 copy //Ace/fixbug1/... //Ace/dev/...
//Ace/dev/foo#1 - branch/sync from //Ace/fixbug1/foo#1
$ p4 submit -d 'Copy changes from task stream to dev'
```

Finally, we free up space in Helix server database tables. To do so, we can either delete or unload the task stream. We cannot work on a task stream after we've deleted it, and it cannot be recovered.

```
$ p4 stream -d //Ace/fixbug1
Stream //Ace/fixbug1 deleted.
```

Alternatively, we can unload the task stream. Unloading gives us the option of recovering the task stream to work with it again. We unload a task stream using the `p4 unload` command. See [p4 unload](#) in *Helix Core P4 Command Reference*.

```
$ p4 unload -s //Ace/fixbug1
Stream //Ace/fixbug1 unloaded.
```

At any time, an unloaded task stream can be reloaded. See [p4 reload](#) in *Helix Core P4 Command Reference*.

```
$ p4 reload -s //Ace/fixbug1
Stream //Ace/fixbug1 reloaded.
```

Task streams and depots

A unique feature of task streams is that it can be in a different depot than its parent. However, generally speaking, the best practice is to use the same depot.

To keep a project depot uncluttered by task streams, your Helix server administrator or project lead might choose to establish a depot for task streams. In this case, create your stream in the task streams depot as a child of a parent in the project depot.

Task stream reuse

When you submit files in your task stream, archives are created in the corresponding depot root folder. Make sure that these archive files are incorporated into your backup processes.

When the work has been completed in the task stream, you can delete it. However, because file content relating to this task stream remains in the archive, it is not possible to create a new task stream with the same name.

When you promote the task stream's changes to the task stream's parent stream, a lazy copy is created rather than a full file copy.

inherit ParentView

Task streams and virtual streams can only have `inherit` ParentViews.

Virtual streams

Virtual streams can be used to create alternative views of real streams. Virtual streams differ from other stream types in that a virtual stream is not a separate set of files, but instead a filtered view of its parent stream. A virtual stream can have child streams, and its child streams inherit its views.

Note

Task streams and virtual streams can only have `inherit` ParentViews.

Stream views and paths

A stream specification has a set of field names (see [p4 stream](#)). The `Paths`, `Remapped`, and `Ignored` fields define the stream "view". These fields control the files and paths that compose a stream and define how those files are propagated.

- A mainline stream has no parent.
- A task streams or a virtual streams always inherits its view from its parent stream.
- A stream of other types can be set to inherit or not inherit from the parent stream.
- To not inherit from the parent stream might be a good choice for a release stream.

To modify the structure of the child, you specify the paths as follows:

Type	Sync?	Submit?	Integrate to/from Parent?	Remarks
share	Y	Y	Y	(Default) For files that are edited and propagated between parent and child streams. All files in a shared path are branched and, in general, shared paths are the least restricted.
isolate	Y	Y	N	For files that must not be propagated outside the stream but can be edited within it, such as binary build results.

Type	Sync?	Submit?	Integrate to/from Parent?	Remarks
<code>import</code>	Y	N	N	<p>Files in this path are mapped as in the parent stream's view (the default) or to <code><depot_path></code> (optional); they are accessible to workspaces but cannot be submitted or integrated to the stream.</p> <p>If <code><view_path></code> is used, it does not necessarily import files from the parent of the stream it was used on; it imports the view. If the parent stream has a parent (grandparent) and the parent's stream view is shared, files are imported from the grandparent stream. An example would be the virtual stream created of a release or development stream, where files are imported from the mainline.</p> <p>If <code><depot_path></code> is used (for files that must be physically present in the stream but are never changed, such as with third-party libraries), it may include a changelist or automatic label specifier (that aliases a changelist) to limit the imported files to the revisions at that change or lower; clients of that stream are limited to seeing revisions at that point in time or lower within that depot path. Use the syntax <code>@changelist#</code>, as in: <code>//depot/lib3.0/...@455678.</code></p>
<code>import+</code>	Y	Y	N	<p>Functions like an import path, in that it can reference an explicitly defined depot path, but unlike a standard import path, you <i>can</i> submit changes to the files in an <code>import+</code> path.</p>

Type	Sync?	Submit?	Integrate to/from Parent?	Remarks
exclude	N	N	N	Files in the parent stream that must never be part of the child stream.

In the following example, files in the **src** path are not submittable (and are imported from the parent stream's view), files in the **lib** path are not submittable (and are imported from an explicitly-specified location in the depot), and files in the **db** path can be edited and submitted in the stream, but can never be copied to the parent:

Paths:

```
share ...
import src/...
import lib/... //depot/lib3.0/...
isolate db/...
```

The paths are used to generate the mappings for workspaces that are associated with the stream. If the stream structure changes, the workspace views are updated automatically and cannot be altered manually. If the stream is locked, only the stream owner (or stream owners, if the **Owner** field of the stream is set to a group) can edit the stream specification.

A stream specification can also remap file locations (so that a file in specified depot location is synced to a different location in the workspace) and screen out files according to file type. For example, to ensure that object files and executables are not part of the stream, add the following entries to the stream specification:

Ignored:

```
.o
.exe
```

Also in this section:

Stream paths and inheritance	96
Stream ParentView Examples	100

Stream paths and inheritance

A stream specification defines the paths that the stream contains and the actions allowed on those paths.

A child stream might or might not inherit its view from its parent stream. When inheritance is enabled, a child stream implicitly inherits from its parent stream. Such a child stream inherits folder paths and behavioral rules from its parent.

Each path is a line in the stream definition. A path contains one or more folders or files. A folder is a path with a wildcard such as ...

Paths	Behavioral Rules
<p>A child normally inherits paths from its parent. However, in the case of a release stream, it might be preferable to not inherit from the parent stream.</p> <p>It is common to filter some files from the parent by excluding them. In this case, the child has fewer paths than the parent.</p> <p>The use of import by a child stream allows the child stream to <i>import</i> files from anywhere in the depot. In this case, the child has more paths than the parent.</p>	<p>Path types can be inherited from parent streams. When they are inherited, you cannot override the effects of the path types assigned by parent streams.</p> <p>Child streams are always as permissive or less permissive than their parents, but never more permissive. For example, if a parent stream defines a path as isolate, its child streams cannot redefine the path as share to enable integrations.</p>

A child stream that inherits its view from its parent cannot add an **isolate** path unless the folders in that path are also included in the parent. The following **Dev** stream can isolate the **config/** folder because that folder is included as a **share** or **isolate** path in **Main**:

```
Stream: //Acme/Main
Parent: none
Paths: share apps/...
       share tests/...
       share config/...

Stream: //Acme/Dev
Parent: //Acme/Main
Paths: share apps/...
       share tests/...
       isolate config/...
```

Example Simple share

Let's start with a simple case: two streams, **//Ace/main** and its child **//Ace/dev**.

```
Stream: //Ace/main
Parent: none
Paths: share ...
```

```
Stream: //Ace/dev
Parent: //Ace/main
Paths: share ...
```

In this case, the entire stream path is shared. When you switch your workspace to the `//Ace/main` stream, the workspace view looks like this:

```
//Ace/main/... //bruno_ws/...
```

The workspace view maps the root of the `//Ace/main` stream to your workspace. When you switch your workspace to the `//Ace/dev` stream, the workspace view is this:

```
//Ace/dev/... //bruno_ws/...
```

And the branch view for `//Ace/dev/` looks like this:

```
//Ace/dev/... //Ace/main/...
```

In other words, the entire `dev` stream can be synced to workspaces, and the entire stream can be branched, merged, and copied.

Example Share and import

Let's look at an example where software components are housed in three separate depots:

`//Acme`, `//Red`, and `//Tango`.

The `Acme` mainline is configured like this:

```
Stream: //Acme/Main
Parent: none
Paths: share apps/...
       share tests/...
       import stuff/... //Red/R6.1/stuff/...
       import tools/... //Tango/tools/...
```

If you switch your workspace to the `//Acme/Main` stream, this would be your workspace view:

```
//Acme/Main/apps/... //bruno_ws/apps/...
//Acme/Main/tests/... //bruno_ws/tests/...
//Red/R6.1/stuff/... //bruno_ws/stuff/...
//Tango/tools/... //bruno_ws/tools/...
```

The stream's `Paths` field lists folders relative to the root of the stream. Those are the folders you get in your workspace, beneath your workspace root. The shared folders are mapped to the `//Acme/Main` path, and the imported paths are mapped to their locations in the `//Red` and `//Tango` depots.

Example Share, isolate, exclude, and import

Let's say that your team doesn't want to do development in the mainline. In this example, XProd feature team has a development stream of their own, defined like this:

```
Stream: //Acme/XProd
Parent: //Acme/Main
Paths: import ...
       isolate apps/bin/...
       share apps/xp/...
       exclude tests/...
```

Switching your workspace to the `//Acme/XProd` stream gives you this view:

```
//Acme/Main/apps/...      //bruno_ws/apps/...
//Acme/XProd/apps/bin/... //bruno_ws/apps/bin/...
//Acme/XProd/apps/xp/...  //bruno_ws/apps/xp/...
//Red/R6.1/stuff/...     //bruno_ws/stuff/...
//Tango/tools/...        //bruno_ws/tools/...
-//Acme/XProd/tests/...  //bruno_ws/tests/...
```

Here we see workspace view inheritance at work. The contents of imported paths are mapped into your workspace. The shared and isolated paths are mapped to the child stream. These contain the files the XProd team is working on and will be submitting changes to. The excluded path (marked with a minus sign in the view) doesn't appear in the workspace at all.

Because the `//Acme/XProd` stream has a parent, it has a branch mapping that can be used by the copy and merge commands. That branch view consists of the following, with only one path shared by the child and parent.

```
-//Acme/XProd/apps/...    //Acme/Main/apps/...
-//Acme/XProd/apps/bin/... //Acme/Main/apps/bin/...
//Acme/XProd/apps/xp/...  //Acme/Main/apps/xp/...
-//Acme/XProd/stuff/...   //Acme/Main/stuff/...
-//Acme/XProd/tests/...   //Acme/Main/tests/...
-//Acme/XProd/tools/...   //Acme/Main/tools/...
```

When you work in an `//Acme/XProd` workspace, it might appear that you're working in a full branch of `//Acme/Main`, but the actual branch is quite small.

Example Child that shares all of the above parent

Let's suppose that Lisa creates a child stream from `//Acme/XProd`. Her stream spec looks like this:

```
Stream: //Acme/LisaDev
Parent: //Acme/XProd
Paths: share ...
```

Lisa's stream has the default view template. Given that Lisa's entire stream path is set to `share`, you might expect that her entire workspace will be mapped to her stream. This is not the case because inherited behaviors take precedence. Sharing applies only to paths that are shared in the parent as well. A workspace for Lisa's stream, with its default view template, has this client view:

```
//Acme/Main/apps/...      //bruno_ws/apps/...
-//Acme/LisaDev/tests/... //bruno_ws/tests/...
//Acme/LisaDev/apps/bin/... //bruno_ws/apps/bin/...
//Acme/LisaDev/apps/xp/... //bruno_ws/apps/xp/...
//Red/R6.1/stuff/...      //bruno_ws/stuff/...
//Tango/tools/...         //bruno_ws/tools/...
```

A workspace in Lisa's stream is the same as a workspace in the XProd stream, with one exception: the paths available for submit are rooted in `//Acme/LisaDev`. If you work in Lisa's stream, you expect to submit changes to her stream.

By contrast, the branch view that maps the `//Acme/Dev` stream to its parent is a branch view that maps only the path that is designated as shared in both streams:

```
-//Acme/Main/apps/...      //XProd/apps/...
-//Acme/LisaDev/tests/...  //XProd/tests/...
-//Acme/LisaDev/apps/bin/... //XProd/apps/bin/...
//Acme/LisaDev/apps/xp/... //bruno_ws/apps/xp/...
-//Red/R6.1/stuff/...      //XProd/stuff/...
-//Tango/tools/...         //XProd/tools/...
```

The default template allows Lisa to:

- branch her own versions of the paths her team is working on, and
- have a workspace with the identical view of non-branched files that she would have in the parent stream.

Stream ParentView Examples

This topic shows:

- how to work with the `ParentView` field and the `--parentview` option of the `p4 streams` command

- the effect of converting `ParentView: inherit` to `ParentView: noinherit`
 - that in the absence of inheritance, you can still integrate from the parent stream to a child with `ParentView: noinherit`

Convert a stream to noinherit

1. Create a mainline stream named `//streams/product1`.

```
p4 stream -t mainline //streams/product1
```

This opens the editor specified by `P4EDITOR`, and presents a populated stream spec.
2. Create a development stream named `//projectX/bruno-dev` as a child of mainline `//projectX/main`.

```
p4 stream -t development -P //projectX/main //projectX/bruno-dev
```

This opens the editor specified by `P4EDITOR`, populated with the stream spec with the Parent and Type fields populated accordingly.
3. For your current client workspace's stream, preview what would happen if the stream were converted to ParentView `noinherit`, but do not actually perform the conversion or open the stream spec:

```
p4 stream parentview -n --noinherit
```
4. This time, add the `-o` option to also print a preview of the converted stream spec.

```
p4 stream parentview -o -n --noinherit
```
5. Assuming you already have a pending changelist 1234, perform the conversion for your current client workspace's stream.

```
p4 stream parentview -c 1234 --noinherit
```

The stream is opened in the current client workspace in the indicated changelist.
6. To make the changes visible to all users, submit the changelist (as you would with any stream spec opened for edit). You can also revert the pending stream spec to abandon the conversion.

Tip

We recommend that you include the `--source-comments` option:


```
p4 stream parentview -c 1234 --source-comments --noinherit
```

because it adds source comments to any `Paths`, `Ignored` or `Remapped` fields that are modified or added as a result of the conversion. These comments are helpful to see how the converted stream view is calculated based on stream specs in the converted streams' ancestry.

Extended example of a conversion to noinherit

The following is an extended example involving several streams to illustrate a conversion.

Assume we have a stream hierarchy in a stream depot named `str` with a mainline stream and three development streams:



mainline

```
Stream: //str/main
Owner: super
Name: main
Parent: none
Type: development
Description:
Mainline
Options: allsubmit unlocked toparent fromparent mergedown
ParentView: inherit
Paths:
share ...
Ignored:
*.o
```

dev1 child

```
Stream: //str/dev1
Owner: super
Name: dev1
Parent: //str/main
Type: development
Description:
Dev1 child
Options: allsubmit unlocked toparent fromparent mergedown
ParentView: inherit
Paths:
share ...
Remapped:
docs/... product_docs/...
```

dev2 grandchild

```
Stream: //str/dev1
Owner: super
Name: dev2
Parent: //str/dev1
Type: development
Description:
Dev2 grandchild
Options: allsubmit unlocked toparent fromparent mergedown
ParentView: inherit
Paths:
share ...
Remapped:
import ssl_libs/... //depot/libs/ssl_libs/v1.0/...
```

dev3 child of dev2

```
Stream: //str/dev2
Owner: super
Name: dev3
Parent: //str/dev2
Type: development
Description:
Created by super.
Options: allsubmit unlocked toparent fromparent mergedown
ParentView: inherit
Paths:
share ...
```

client workspace view of dev3

Because all the streams are ParentView `inherit`, the client workspace view for workspaces of `//str/dev3` is the inherited result of all streams back to the `//str/main` mainline stream:

Stream: `//str/dev3`

View:

```
//str/dev3/... //super_client/...
//depot/libs/ssl/1.0a/... //super_client/ssl_libs/...
//str/dev3/docs/... //super_client/product-docs/...
-//str/...%%1.o //super_client/...%%1.o
```

The view reflects all that has been inherited:

- The mainline `//str/main` has an Ignored entry for files ending in `*.o`
- Its child, `//str/dev1`, remaps the `docs` path to a different name, `product-docs`.
- The next stream, `//str/dev2`, adds a Paths line to import an SSL library from a non-streams location.
- Finally, `//str/dev3` has Paths `share ...`

converting dev3 to noinherit

A user of stream `//str/dev3` converts the stream from ParentView: `inherit` to ParentView: `noinherit`, including source comments, and submits the resulting converted spec:

```
p4 stream parentview --source-comments --noinherit
p4 submit -So -d "Converting dev3 to noinherit"
```

After conversion:

- the client workspace view for a workspace of `//str/dev3` remains unchanged
- the Paths field of `//str/dev3` does change:

```

Stream: //str/dev3
Update: 2020/11/05 11:30:02
Access: 2020/11/05 11:42:21
Owner: super
Name: dev3
Parent: //str/dev2
Type: development
Description:
Created by super.
Options: allsubmit unlocked toparent fromparent mergedown
ParentView: noinherit
Paths:
import ssl_libs/... //depot/libs/ssl/1.0a/... ## merge from
//str/dev2@8
share ...
Remapped:
docs/... product-docs/... ## copy from //str/dev1@9
Ignored:
*.o ## copy from //str/main@7

```

where

- the ParentView field is now `noinherit`
- The `Paths`, `Ignored` and `Remapped` fields in `//str/dev3` have been updated based on the contents of the fields in all ancestor streams
- The comments indicate from which stream the changes originated, and if they were copied or merged into the resulting stream

integrating a stream spec from its parent

Suppose another user modifies the `Paths` field of `//str/dev2` by changing the SSL library version from `1.0a` to `1.1.1h`:

```

Paths:
share ...
import ssl_libs/... //depot/libs/ssl/1.1.h/...

```

Because `dev3` was converted to `ParentView: noinherit`, its client workspace view does not inherit this change and still reflects the original import path of `1.0a`.

To make `//str/dev3` reflect this change, perform a stream spec integration from its parent, `//str/dev2`:

```
p4 integrate -r -As -S //str/dev3
```

```
Stream spec //str/dev3@5 - integrate field Paths from //str/dev2@10
```

Resolve any differences with the `p4 resolve` command. In this case, the user chooses to accept the changes from `//str/dev2` with `at`, which means "accept theirs":

```

p4 resolve -So
//str/dev3 Paths - resolving //str/dev2@10
Paths resolve:
at: import ssl_libs/... //depot/libs/ssl/1.1.h/...
ay: import ssl_libs/... //depot/libs/ssl/1.0a/... ## merge from
//str/dev2@8
am: merge of both
Accept(a) Skip(s) Help(?) am: at
//str/dev3 Paths - copy from //str/dev2@10

```

The stream spec is open (for integrate) in the current client workspace, and the user can inspect what the client view would be with the new spec:

View:

```

//str/dev3/... //super_client/...
//depot/libs/ssl/1.1.h/... //super_client/ssl_libs/...
//str/dev3/docs/... //super_client/product-docs/...
-//str/...%1.0 //super_client/...%1.0

```

The client workspace view for the client of `//str/dev3` now reflects the change made to the Paths field of stream `//str/dev2`.

Because `//str/dev3` has a `noinherit` ParentView, no implicit inheritance occurred. Instead, we performed an explicit integration and resolve. To make the changes to `//str/dev3` visible to all users, the user submits the pending change. This affects all client workspaces of the `//str/dev3` stream.

Update streams

As part of maintaining your version control application, you might:

- modify the paths of the stream to:
 - change the version of an included library by modifying the target of an `import` path
 - change the scope of a path to widen or narrow the scope included
- Change restrictions on who can submit to the stream

To do this, modify the stream specification:

- (new in 2019.1 and recommended) use the [Private editing of streams feature of p4 stream](#). This includes the `-So`, `-Si`, or `-Sx` options of `p4 edit`, `p4 submit`, `p4 revert`, and `p4 resolve`. These options give you control of when your changes will affect other users. We recommend that you:
 - isolate your work in progress so that other users of the stream are not impeded
 - make edits to the stream spec visible through a changelist (see "[Changelist reporting](#)" on page 159)

- (prior to 2019.1 and still supported) use the `p4 stream` command, which **immediately** updates all workspace views derived from that stream

The table below shows the recommended commands.

Edit a stream

Recommended	Still Supported
<code>p4 edit -So</code>	<code>p4 stream edit</code>
<p>Puts your client's stream spec into the "opened" state, isolating any edits made to fields that affect view generation. While the spec is open, these fields are marked with the comment "#open" to indicate that they are open and isolated to your client. Changes made to these fields affect your client's view only. Other clients' views are not affected.</p>	

Resolve a stream

Recommended	Still Supported
<code>p4 resolve -So</code>	<code>p4 stream resolve</code>
<p>Resolves changes that have been submitted to the stream spec since you opened it. You cannot submit changes to the stream spec until newer changes have been resolved.</p>	

Revert a stream

Recommended	Still Supported
<code>p4 revert -So</code>	<code>p4 stream revert</code> reverts any pending changes made to the open stream spec, returning your client to the latest submitted version of the stream.
<p>Reverts any pending changes made to the open stream spec, returning your client to the latest submitted version of the stream.</p>	

Submit, shelve, and unshelve a stream

placeholder for what we want to say about ???:

p4 submit

p4 shelve

p4 unshelve

Resolve conflicts

In settings where multiple users are working on the same set of files, conflicts can occur. Helix server enables your team to work on the same files simultaneously and resolve any conflicts that arise. For example, conflicts occur if two users change the same file (the primary concern in team settings) or you edit a previous revision of a file rather than the head revision.

When you attempt to submit a file that conflicts with the head revision in the depot, Helix server requires you to resolve the conflict.

Merging changes from a development stream to a release stream is another typical task that requires you to resolve files.

To prevent conflicts, Helix server enables you to lock files when they are edited. However, locking can restrict team development. Your team needs to choose the strategy that maximizes file availability while minimizing conflicts. For details, see "Locking files" on page 128.

How conflicts occur	109
How to resolve conflicts	110
Your, theirs, base, and merge files	110
Options for resolving conflicts	111
Accepting yours, theirs, or merge	112
Editing the merge file	113
Merging to resolve conflicts	113
Full list of resolve options	113
Resolving branched files, deletions, moves and filetype changes	115
Resolve command-line options	117
Resolve reporting commands	118

How conflicts occur

Conflicts can occur in a number of ways, for example:

1. Bruno opens `//JamCode/dev/jam/command.c#8` for edit.
2. Gale subsequently opens the same file for edit in her own client workspace.
3. Bruno and Gale both edit `//Jamcode/dev/jam/command.c#8`.
4. Bruno submits a changelist containing `//JamCode/dev/jam/command.c`, and the submit succeeds.
5. Gale submits a changelist with her version of `//Acme/dev/jam/command.c`. Her submit fails.

If Helix server accepts Gale's version into the depot, her changes will overwrite Bruno's changes. To prevent Bruno's changes from being lost, Helix server rejects the changelist and schedules the conflicting file to be resolved. If you know of file conflicts in advance and want to schedule a file for resolution, sync it. Helix server detects the conflicts and schedules the file for resolution.

How to resolve conflicts

To resolve a file conflict, you determine the contents of the files you intend to submit by issuing the `p4 resolve` command and choosing the desired method of resolution for each file. After you resolve conflicts, you submit the changelist containing the files.

Note

If you open a file for edit, then sync a subsequently submitted revision from the depot, Helix server requires you to resolve to prevent your own changes from being overwritten by the depot file.

By default, Helix server uses its diff program to detect conflicts. You can configure a third-party diff program. For details, see ["Diff files" on page 53](#).

To resolve conflicts and submit your changes, perform the following steps:

1. Sync the files (for example `p4 sync //Acme/dev/jam/...`). Helix server detects any conflicts and schedules the conflicting files for resolve.
2. Issue the `p4 resolve` command and resolve any conflicts. See ["Options for resolving conflicts" on the facing page](#) for details about resolve options.
3. Test the resulting files (for example, compile code and verify that it runs).
4. Submit the changelist containing the files.

Note

If any of the three file revisions participating in the merge are binary instead of text, a three-way merge is not possible. Instead, `p4 resolve` performs a two-way merge: the two conflicting file versions are presented, and you can choose between them or edit the one in your workspace before submitting the changelist.

Your, theirs, base, and merge files

The `p4 resolve` command uses the following terms during the merge process:

File revision	Description
<i>yours</i>	The revision of the file in your client workspace, containing changes you made.
<i>theirs</i>	The revision in the depot, edited by another user, that yours conflicts with. (Usually the head revision, but you can schedule a resolve with another revision using <code>p4 sync</code> .)
<i>base</i>	The file revision in the depot that <i>yours</i> and <i>theirs</i> were edited from (the closest common ancestor file).
<i>merge</i>	The file generated by Helix server from <i>theirs</i> , <i>yours</i> , and <i>base</i> .

File revision	Description
<i>result</i>	The final file resulting from the resolve process.

Options for resolving conflicts

To specify how a conflict is to be resolved, you issue the `p4 resolve` command, which displays a dialog for each file scheduled for resolve. The dialog describes the differences between the file you changed and the conflicting revision. For example:

```
C:\bruno_ws> p4 resolve //Acme/dev/jam/command.c
c:\bruno_ws\dev\main\jam\command.c - merging
//Acme/dev/jam/command.c#9
```

```
Diff chunks: 4 yours + 2 theirs + 1 both + 1 conflicting
Accept(a) Edit(e) Diff(d) Merge (m) Skip(s) Help(?) e:
```

The differences between each pair of files are summarized by `p4 resolve`. Groups of lines (chunks) in the **yours**, **theirs**, and **base** files can differ in various ways. Chunks can be:

- **Diffs:** different between two of the three files: *yours*, *theirs*, or *base*
- **Conflicts:** different in all three files

In the preceding example:

- Four chunks are identical in *theirs* and *base* but are different in *yours*.
- Two chunks are identical in *yours* and *base* but are different in *theirs*.
- One chunk was changed identically in *yours* and *theirs*.
- One chunk is different in *yours*, *theirs*, and *base*.

Helix server's recommended choice is displayed at the end of the command line. Pressing **Enter** or choosing **Accept** performs the recommended choice.

You can resolve conflicts in three basic ways:

- Accept a file without changing it (see ["Accepting yours, theirs, or merge"](#) on the next page)
- Edit the merge file with a text editor (see ["Editing the merge file"](#) on page 113)
- Merge changes selectively using a merge program (see ["Merging to resolve conflicts"](#) on page 113)

The preceding options are interactive. You can also specify resolve options on the `p4 resolve` command line, if you know which file you want to accept. For details, see "Resolve command-line options" on page 117. To re-resolve a resolved but unsubmitted file, specify the `-f` option when you issue the `p4 resolve` command. You cannot re-resolve a file after you submit it. The following sections describe the resolve options in more detail.

Also in this section:

Accepting yours, theirs, or merge	112
Editing the merge file	113
Merging to resolve conflicts	113

Accepting yours, theirs, or merge

To accept a file without changing it, specify one of the following options:

Option	Description	Remarks
<code>a</code>	Accept recommended file	<ul style="list-style-type: none"> ▪ If <i>theirs</i> is identical to <i>base</i>, accept <i>yours</i>. ▪ If <i>yours</i> is identical to <i>base</i>, accept <i>theirs</i>. ▪ If <i>yours</i> and <i>theirs</i> are different from <i>base</i>, and there are no conflicts between <i>yours</i> and <i>theirs</i>; accept <i>merge</i>. ▪ Otherwise, there are conflicts between <i>yours</i> and <i>theirs</i>, so skip this file.
<code>ae</code>	Accept edit	If you edited the <i>merge</i> file (by selecting <code>e</code> from the <code>p4 resolve</code> dialog), accept the edited version into the client workspace. The version in the client workspace is overwritten.
<code>am</code>	Accept <i>merge</i>	Accept <i>merge</i> into the client workspace as the resolved revision. The version in the client workspace is overwritten.
<code>at</code>	Accept <i>theirs</i>	Accept <i>theirs</i> into the client workspace as the resolved revision. The version in the client workspace is overwritten.
<code>ay</code>	Accept <i>yours</i>	Accept <i>yours</i> into the client workspace as the resolved revision, ignoring changes that might have been made in <i>theirs</i> .

Accepting *yours*, *theirs*, *edit*, or *merge* overwrites changes, and the generated merge file might not be precisely what you want to submit to the depot. The most precise way to ensure that you submit only the desired changes is to use a merge program or edit the merge file.

Editing the merge file

To resolve files by editing the merge file, choose the **e** option. Helix server launches your default text editor, displaying the merge file. In the merge file, diffs and conflicts appear in the following format:

```
>>>> ORIGINAL file#n(text from the original version)
==== THEIR file#m(text from their file)
==== YOURS file(text from your file)
<<<<
```

To locate conflicts and differences, look for the difference marker **>>>>** and edit that portion of the text. Examine the changes made to *theirs* to make sure that they are compatible with your changes. Make sure you remove all conflict markers before saving. After you make the desired changes, save the file. At the **p4 resolve** prompt, choose **ae**.

By default, only the conflicts between the *yours* and *theirs* files are marked. To generate difference markers for all differences, specify the **-v** option when you issue the **p4 resolve** command.

Merging to resolve conflicts

A merge program displays the differences between yours, theirs, and the base file, and enables you to select and edit changes to produce the desired result file. To configure a merge program, set **P4MERGE** to the desired program. To use the merge program during a resolve, choose the **m** option. For details about using a specific merge program, consult its online help.

After you merge, save your results and exit the merge program. At the **p4 resolve** prompt, choose **am**.

Full list of resolve options

The **p4 resolve** command offers the following options:

Option	Action	Remarks
?	Help	Display help for p4 resolve .
a	Accept automatically	Accept the auto-selected file: <ul style="list-style-type: none"> ▪ If <i>theirs</i> is identical to <i>base</i>, accept <i>yours</i>. ▪ If <i>yours</i> is identical to <i>base</i>, accept <i>theirs</i>. ▪ If <i>yours</i> and <i>theirs</i> are different from <i>base</i>, and there are no conflicts between <i>yours</i> and <i>theirs</i>, accept <i>merge</i>. ▪ Otherwise, there are conflicts between <i>yours</i> and <i>theirs</i>, so skip this file.

Option	Action	Remarks
ae	Accept edit	If you edited the <i>merge</i> file (by selecting e from the p4 resolve dialog), accept the edited version into the client workspace. The version in the client workspace is overwritten.
am	Accept <i>merge</i>	Accept <i>merge</i> into the client workspace as the resolved revision. The version in the client workspace is overwritten.
at	Accept <i>theirs</i>	Accept <i>theirs</i> into the client workspace as the resolved revision. The version in the client workspace is overwritten.
ay	Accept <i>yours</i>	Accept <i>yours</i> into the client workspace as the resolved revision, ignoring changes that might have been made in <i>theirs</i> .
d	Diff	Show diffs between <i>merge</i> and <i>yours</i> .
dm	Diff <i>merge</i>	Show diffs between <i>merge</i> and <i>base</i> .
dt	Diff <i>theirs</i>	Show diffs between <i>theirs</i> and <i>base</i> .
dy	Diff <i>yours</i>	Show diffs between <i>yours</i> and <i>base</i> .
e	Edit merged	Edit the preliminary merge file generated by Helix server.
et	Edit <i>theirs</i>	Edit the revision in the depot that the client revision conflicts with (usually the head revision). This edit is read-only.
ey	Edit <i>yours</i>	Edit the revision of the file currently in the workspace.
m	Merge	Invoke the command P4MERGE base theirs yours merge . To use this option, you must set P4MERGE to the name of a third-party program that merges the first three files and writes the fourth as a result.
s	Skip	Skip this file and leave it scheduled for resolve.

Note

The *merge* file is generated by the Helix server, but the differences displayed by **dy**, **dt**, **dm**, and **d** are generated by your computer's diff program. To configure another diff program to be launched when you choose a **d** option during a resolve, set **P4DIFF**. For more details, see "Diff files" on page 53.

Example Resolving file conflicts

To resolve conflicts between his work on a Jam **README** file and Gale's work on the same file, Bruno types **p4 resolve //Acme/dev/jam/README** and sees the following:

```
Diff chunks: 0 yours + 0 theirs + 0 both + 1 conflicting
Accept(a) Edit(e) Diff(d) Merge (m) Skip(s) Help(?) e: e
```

Bruno sees that he and Gale have made a conflicting change to the file. He types `e` to edit the merge file and searches for the difference marker `>>>>`. The following text is displayed:

```
Jam/MR (formerly "jam - make(1) redux")
/+\
>>>> ORIGINAL README#26
      +\ Copyright 1993, 1997 Christopher Seiwald.
==== THEIRS README#27
      +\ Copyright 1993, 1997, 2004 Christopher Seiwald.
==== YOURS README
      +\ Copyright 1993, 1997, 2005 Christopher Seiwald.
<<<<
      \+/
```

Bruno and Gale have updated the copyright date differently. Bruno edits the merge file so that the header is correct, exits from the editor and types `am`. The edited merge file is written to the client workspace, and he proceeds to resolve the next file.

When a version of the file is accepted during a resolve, the file in the workspace is overwritten, and the new client file must still be submitted to the depot. New conflicts can occur if new versions of a file are submitted after you resolve but before you submit the resolved files. This problem can be prevented by locking the file before you perform the resolve. For details, see ["Locking files" on page 128](#).

Resolving branched files, deletions, moves and filetype changes

Beyond reconciling changes to the contents of related files after integration, you can also determine how other kinds of changes are handled. Consider this example:

- You edit `header.cc` in the mainline while a coworker deletes it in the release branch (or vice versa). You integrate fixes in the release branch back to main. During resolve, you can decide whether `header.cc` is deleted from the mainline or the action in the release branch is ignored, preserving `header.cc` in the mainline.
- A developer implements RCS keywords in source files in a development branch, and changes their Helix server filetype from `text` to `text+k`. The release manager wants to integrate new features from the development branch to the mainline, but does not want to enable keyword expansion in the mainline. During resolve, the release manager can choose to ignore the filetype change.
- The file `header.cc` is branched from `main` to `rel`. Subsequently, it's renamed to `headerx.cc` in main, and moved in the release branch to the `headers` subfolder.

Following are simple cases describing how you can resolve non-content changes to related files. After a source file is branched to a target file, changes are made as describe below, then you integrate the source to the target. To choose the outcome, you specify the resolve options **at** (“Accept Theirs”) or **ay** (“Accept Yours”) as follows:

- **The source is edited and target is deleted:** the **at** option re-adds the source in the target branch. The **ay** option causes the file to remain deleted in the target branch.
- **The source is deleted and the target is edited:** the **at** option causes the file to be deleted in the target branch. The **ay** option retains the edited content in the target branch.
- **The target file was moved after being branched:** the **at** option moves the target file to the source file name and location. The **ay** option retains the target file name and location.
- **The filetype of the source file was changed after it was branched:** the **at** option propagates the change to the target. The **ay** option leaves the filetype of the target unchanged. If the differing filetypes do not conflict, you have the option of combining them.
- **Files have been moved or renamed in conflicting ways:** you are prompted to choose a path and filename. Example:

```
Resolving move to //Acme/rel/headerx.cc
Filename resolve:
at: //Acme/rel/headerx.cc
ay: //Acme/rel/headers/header.cc
am: //Acme/rel/headers/headerx.cc
```

By default, the **p4 resolve** command resolves all types of change, content and non-content. To constrain the type of actions that you want to resolve, specify the **-A** option as follows:

Option	What is Resolved
-Aa	Resolve attributes set by p4 attribute .
-Ab	Integrations where the source is edited and the target is deleted.
-Ac	Resolve file content changes as well as actions.
-Ad	Integrations where the source is deleted and target is edited.
-Am	Renames and moves.
-At	Filetype changes.
-AQ	Charset changes.

To perform more than one type of resolve, combine the options (for example: **-Abd**). By default, resolving is performed file by file, interactively. To specify the same outcome for a particular action (for example, propagate all moves), and avoid the prompting, include the desired option on the command line. For example: **p4 resolve -Am -at**

Resolve command-line options

The `p4 resolve` options described below enable you to resolve directly instead of interactively. When you specify one of these options in the `p4 resolve` command, files are resolved as described in the following table:

Option	Description
<code>-a</code>	Accept the auto-selected file.
<code>-ay</code>	Accept <i>yours</i> .
<code>-at</code>	Accept <i>theirs</i> . Use this option with caution, because the file revision in your client workspace is overwritten with the head revision from the depot, and you cannot recover your changes.
<code>-am</code>	Accept the recommended file revision according to the following logic: <ul style="list-style-type: none"> ▪ If <i>theirs</i> is identical to <i>base</i>, accept <i>yours</i>. ▪ If <i>yours</i> is identical to <i>base</i>, accept <i>theirs</i>. ▪ If <i>yours</i> and <i>theirs</i> are different from <i>base</i>, and there are no conflicts between <i>yours</i> and <i>theirs</i>, accept <i>merge</i>. ▪ Otherwise, there are conflicts between <i>yours</i> and <i>theirs</i>, so skip this file, leaving it unresolved.
<code>-af</code>	Accept the recommended file revision, even if conflicts remain. If this option is used, edit the resulting file in the workspace to remove any difference markers.
<code>-as</code>	Accept the recommended file revision according to the following logic: <ul style="list-style-type: none"> ▪ If <i>theirs</i> is identical to <i>base</i>, accept <i>yours</i>. ▪ If <i>yours</i> is identical to <i>base</i>, accept <i>theirs</i>. ▪ Otherwise skip this file.

Example Automatically accepting particular revisions of conflicting files

Bruno has been editing the documentation files in `/doc` and knows that some of them require resolving. He types `p4 sync doc/*.guide`, and all of these files that conflict with files in the depot are scheduled for resolve.

He then types `p4 resolve -am` and the merge files for all scheduled resolves are generated, and those merge files that contain no line set conflicts are written to his client workspace. He'll still need to manually resolve any conflicting files, but the amount of work he needs to do is substantially reduced.

Resolve reporting commands

The following reporting commands are helpful when you are resolving file conflicts:

Command	Meaning
<code>p4 diff</code> <code>[filenames]</code>	Differs the file revision in the workspace with the last revision you synced, to display changes you have made.
<code>p4 diff2</code> <code>file1 file2</code>	Differs two depot files. The specified files can be any two file revisions and different files. When you diff depot files, Helix server uses its own diff program, not the diff program configured by setting <code>P4DIFF</code> .
<code>p4 sync -n</code> <code>[filenames]</code>	Previews the specified sync, listing which files have conflicts and need to be resolved.
<code>p4 resolved</code>	Reports files that have been resolved but not yet submitted.

Codeline management

This chapter describes the tasks required to maintain groups of files in your depot. The following specific issues are addressed:

- Depot directory structure and how to best organize your repository
- Moving files and file changes among stream and project directories
- Identifying specific sets of files using either labels or changelists

This chapter focuses on maintaining a software codebase, but many of the tasks are relevant to managing other groups of files, such as a web site.

Organizing the depot	119
Branching streams (introduction)	120
A shortcut: p4 populate	121
Branching streams (merge)	121
When to branch	122
Branching streams	122
Merge changes	123
Merging between unrelated files	124
Merging specific file revisions	125
Re-merging and re-resolving files	125
Reporting branches and merges	125

Organizing the depot

You can think of a depot as a top-level directory. Consider the following factors as you decide how to organize your depot:

- **Type of content:** create depots or mainline streams according to the nature of your projects and their relationships (for example, applications with multiple components developed on separate schedules).
- **Release requirements:** within a project, create streams for each release and merge changes between branches to control the introduction of features and bug fixes.
- **Build management:** use labels and changelists to control the file revisions that are built; use client specifications and views to ensure clean build areas.

A basic and logical way to organize the depot is to create one subdirectory (stream) for each project. For example, if your company is working on Jam, you might devote one stream to the release presently in development, another to already-released software, and perhaps one to your corporate web site. Your developers can modify their workspace views to map the files in their project, excluding other projects that are not of interest. For example, if Earl maintains the web site, his workspace view might look like this:

```
//JamCode/www/dev/... //earl-web-catalpa/www/development/...
//JamCode/www/review/... //earl-web-catalpa/www/review/...
//JamCode/www/live/... //earl-web-catalpa/www/live/...
```

And Gale, who's working on Jam, sets up her workspace view as:

```
//Jamcode/dev/jam/... //gale-jam-oak/jam/...
```

You can organize according to projects or according to the purpose of a stream. For example, to organize the depot according to projects, you can use a structure like the following:

```
//Acme/project1/main/
//Acme/project1/release 1.0/
//Acme/project1/release 1.1/
```

Or, to organize the depot according to the purpose of each stream, you can use a structure like the following:

```
//Acme/main/project1/
//Acme/main/project2/
//Acme/release1.0/project1/
//Acme/release1.0/project2/
//Acme/release2.0/project1/
//Acme/release2.0/project2/
```

Another approach is to create one depot for each project. Choose a structure that makes branching and merging as simple as possible, so that the history of your activities makes sense to you.

Branching streams (introduction)

If you are branching from a stream that has no history, use the `p4 add` command to add files to it, then use `p4 copy` to create the branched streams. For example, to create the mainline structure shown in the previous section, perform the following steps:

1. Create a local folder your workspace for the mainline files; for example:

```
$ mkdir c:\p4clients\myworkspace\depot\main\
```

2. Copy the files for Project1 and Project2 to the newly created folder.
3. Add the files to the depot:

```
$ p4 add //Acme/main/project1/...
$ p4 add //Acme/main/project2/...
$ p4 submit
```

4. Create release streams:

```
$ p4 copy //Acme/main/project1/... //Acme/release1.0/project1/...
$ p4 copy //Acme/main/project2/... //Acme/release1.0/project2/...
$ p4 submit
```

Now you can use the `p4 copy` and `p4 merge` commands to propagate changes between main and release streams.

If there is a historical relationship between the source and target that you need to preserve, "seed" a stream from another stream using the `p4 integrate` command, .

Also in this section:

[A shortcut: p4 populate](#)121

A shortcut: p4 populate

If a target stream is completely empty (no files present, not even deleted files), Helix server offers a command that automates the process of **copying** the files from an existing source stream and **submitting** the associated changelist.

For example, instead of populating a `release1.0` branch with the following two commands,

```
$ p4 copy //Acme/main/project1/... //Acme/release1.0/project1/...
$ p4 submit
```

you can use the `p4 populate` command to populate the stream with a single command:

```
$ p4 populate //Acme/main/project1/... //Acme/release1.0/project1/...
```

Branching streams (merge)

Branching is a method of maintaining the relationship between sets of related files. Branches can evolve separately from their ancestors and descendants, and you can propagate (merge) changes from one branch to another as desired.

To create a stream, use the `p4 merge` command. The `p4 merge` command is also used to propagate changes between existing sets of files. For details about merging changes, see "Merge changes" on page 123.

Also in this section:

[When to branch](#)122
[Branching streams](#)122

When to branch

Create a branch when two sets of files have different submission policies or need to evolve separately. For example:

- *Problem* : the development group wants to submit code to the depot whenever their code changes, regardless of whether it compiles, but the release engineers don't want code to be submitted until it's been debugged, verified, and approved.

Solution: create a release branch by branching the development codeline. When the development codeline is ready, it is merged into the release codeline. Patches and bug fixes are made in the release code and merged back into the development code.
- *Problem*: a company is writing a driver for a new multi-platform printer. The UNIX device driver is done and they are beginning work on an OS X driver, using the UNIX code as their starting point.

Solution: create an OS X branch from the existing UNIX code. These two codelines can evolve separately. If bugs are found in one codeline, fixes can be merged to the other.

One basic strategy is to develop code in a mainline stream and create streams for releases. Make release-specific bug fixes in the release streams and, if required, merge them back into the mainline stream.

Branching streams

To branch a stream, use the `p4 branch` command. When you branch a stream, Helix server records the relationships between the branched files and their ancestors.

You can create branches using file specifications or branch specifications. For simple branches, use file specifications. For branches that are based on complex sets of files or to ensure that you have a record of the way you defined the branch, use branch specifications. Branch specifications can also be used in subsequent integrations. Branch specifications also can serve as a record of codeline policy.

Using branch specifications

To map a set of files from source to target, you can create a *branch mapping* and use it as an argument when you issue the `p4 integrate` command. To create a branch mapping, issue the `p4 branch branchname` command and specify the desired mapping in the **View:** field, with source files on the left and target files on the right. Make sure that the target files and directories are in your client view. Creating or altering a branch mapping has no effect on any files in the depot or client workspace. The branch mapping merely maps source files to target files.

To use the branch mapping to create a branch, issue the `p4 integrate -b branchname` command; then use `p4 submit` to submit the target files to the depot.

Branch specifications can contain multiple mappings and exclusionary mappings, just as client views can. For example, the following branch mapping branches the `Jam 1.0` source code, excluding test scripts, from the main codeline:

```
Branch:   jamgraph-1.0-dev2release

View:
  //depot/dev/main/jamgraph/...
//depot/release/jamgraph/1.0/...
  -//depot/dev/main/jamgraph/test/...
//depot/release/jamgraph/1.0/test/...
  //depot/dev/main/bin/glut32.dll
//depot/release/jamgraph/1.0/bin/glut32.dll
```

To create a branch using the preceding branch mapping, issue the following command:

```
$ p4 integrate -b jamgraph-1.0-dev2release
```

and use **p4 submit** to submit the changes.

To delete a branch mapping, issue the **p4 branch -d *branchname*** command. Deleting a branch mapping has no effect on existing files or branches.

As with workspace views, if a filename or path in a branch view contains spaces, make sure to quote the path:

```
//depot/dev/main/jamgraph/... "//depot/release/Jamgraph 1.0/..."
```

Merge changes

After you create branches, you might need to propagate changes between them. For example, if you fix a bug in a release branch, you probably want to incorporate the fix back into your main codeline. To propagate selected changes between branched files, you use the **p4 merge** and **p4 resolve** commands, as follows:

1. Issue the **p4 merge** command to schedule the files for resolve.
2. Issue the **p4 resolve** command to propagate changes from the source files to the target files.

To propagate individual changes, edit the merge file or use a merge program. The changes are made to the target files in the client workspace.

3. Submit the changelist containing the resolved files.

Example Propagating changes between branched files

Bruno has fixed a bug in the release 2.2 branch of the Jam project and needs to integrate it back to the main codeline. From his home directory, Bruno types the following:

```
$ p4 merge //JamCode/release/jam/2.2/src/Jambase
//JamCode/dev/jam/Jambase
```

He sees the following message:

```
//JamCode/dev/jam/Jambase#134 - merge from
///JamCode/release/jam/2.2/src/Jambase#9
```

The file has been scheduled for resolve. He types **p4 resolve**, and the standard merge dialog appears on his screen.

```
//JamCode/dev/jam/Jambase - merging
depot/release/jam/2.2/src/Jambase#9
Diff chunks: 0 yours + 1 theirs + 0 both + 0 conflicting
Accept(a) Edit(e) Diff(d) Merge (m) Skip(s) Help(?) [at]:
```

He resolves the conflict. When he's done, the result file overwrites the file in his workspace. The changelist containing the file must be submitted to the depot.

To run the **p4 merge** or **p4 copy** commands, you must have Helix server **write** permission on the target files, and **read** access on the source files. (See the [Helix Core Server Administrator Guide](#) for information on Helix server permissions.)

By default, a file that has been newly created in a client workspace by **p4 merge** cannot be edited before being submitted. To edit a newly merged file before submission, resolve it, then issue the **p4 edit** command.

If the range of revisions being merged includes deleted revisions (for example, a file was deleted from the depot, then re-added), you can specify how deleted revisions are merged using the **-Di** option. For details, refer to the [Helix Core P4 Command Reference](#).

Also in this section:

Merging between unrelated files	124
Merging specific file revisions	125
Re-merging and re-resolving files	125
Reporting branches and merges	125

Merging between unrelated files

If the target file was not branched from the source, there is no *base* (common ancestor) revision, and Helix server uses the first (most recently added) revision of the source file as its base revision. This operation is referred to as a *baseless merge*.

Merging specific file revisions

By default, the `p4 merge` command merges all the revisions following the last-merged source revision into the target. To avoid having to manually delete unwanted revisions from the merge file while editing, you can specify a range of revisions to be merged. The *base* file is the revision with the most edits in common.

Example Merging specific file revisions

Bruno has made two bug fixes to `//JamCode/dev/jam/scan.c` in the development stream, and Earl wants to merge the change into the release 1.0 branch. Although `scan.c` has gone through several revisions since the fixes were submitted, Earl knows that the bug fixes he wants were made to the 30th revision of `scan.c`. He types:

```
$ p4 integrate -b jamgraph-1.0-dev2release
depot/release/jam/1.0/scan.c#30,30
```

The target file (`//depot/release/jam/1.0/scan.c`) is given as an argument, but the file revisions are applied to the source. When Earl runs `p4 resolve`, only the 30th revision of Bruno's file is scheduled for resolve. That is, Earl sees only the changes that Bruno made to `scan.c` at revision 30.

Re-merging and re-resolving files

After a revision of a source file has been merged into a target, that revision is skipped in subsequent merges to the same target. To force the merging of already-merged files, specify the `-f` option when you issue the `p4 merge` command.

A target that has been resolved but not submitted can be resolved again by specifying the `-f` option to `p4 resolve`. When you re-resolve a file, *yours* is the new client file, the result of the original resolve.

Reporting branches and merges

The reporting commands below provide useful information about the status of files being branched and merged. Note the use of the preview option (`-n`) for reporting purposes.

To display this information	Use this command
Preview of the results of an integration	<code>p4 integrate -n [filepatterns]</code>
Files that are scheduled for resolve	<code>p4 resolve -n [filepatterns]</code>
Files that have been resolved but not yet submitted.	<code>p4 resolved</code>

To display this information	Use this command
List of branch specifications	<code>p4 branches</code>
The integration history of the specified files.	<code>p4 integrated <i>filepatterns</i></code>
The revision histories of the specified files, including the integration histories of files from which the specified files were branched.	<code>p4 filelog -i [<i>filepatterns</i>]</code>

Less common tasks

This chapter discusses less common tasks.

Work offline	127
Ignoring groups of files when adding	128
Locking files	128
Preventing multiple resolves by locking files	129
Preventing multiple checkouts	129

Work offline

The preferred method of working offline (without access to the Helix server) is to use DVCS (distributed versioning) features. For details, refer to *Using Helix Core Server for Distributed Versioning*.

If you work offline, you must manually reconcile your work with the Helix server service when you regain access to it. The following method for working detached assumes that you work on files in your workspace or update the workspace with your additions, changes, and deletions before you update the depot:

To work offline:

1. Work on files without issuing `p4` commands. Instead, use operating system commands to change the permissions on files.
2. After the network connection is re-established, use `p4 status` or `p4 reconcile` to find all files in your workspace that have changed.
3. Submit the resulting changelist(s).

To detect changed files, issue the `p4 status` or `p4 reconcile` commands. The commands perform essentially the same function, but differ in their default behavior and output format.

Command	Description
<code>p4 reconcile</code>	When called without arguments, <code>p4 reconcile</code> opens the files in a changelist. To preview an operation, you must either use the <code>-n</code> option with <code>p4 reconcile</code> , or use the <code>p4 status</code> command.
<code>p4 status</code>	When called without arguments, <code>p4 status</code> only previews the results of the workspace reconciliation. You must use either <code>p4 status -A</code> (or some combination of the <code>-e</code> , <code>-a</code> , or <code>-d</code> options) to actually open the files in a changelist.

Also in this section:

Ignoring groups of files when adding

Sometimes development processes result in the creation of extraneous content that should not be submitted to the depot. Possible examples:

- compilers produce object files and executables during development
- text editors and word processors produce backup files
- some individuals might have informal notes on work in progress

To ignore files (or groups of files) when adding to the depot:

1. Create a file with a list of file specifications to ignore.
2. Set the `P4IGNORE` environment variable to point to this file.

When you add files, the full local path and parent directories of any file to be added are searched for `P4IGNORE` files. If any `P4IGNORE` files exist, their rules are added to a list, with greater precedence given to `P4IGNORE` rules closest to the file being added. For details on syntax and an example, see `P4IGNORE` in the *Helix Core P4 Command Reference*.

To override the `P4IGNORE` file, use the `-I` option with the `p4 add`, `p4 reconcile`, or `p4 status` commands.

Reporting ignored files

The `p4 ignores` command reports the ignore mappings in effect. Specifically, it displays the ignore mappings from the rules in the `P4IGNORE` file. If you add the `-i` option, it reports whether a particular file (or set of files) will be ignored.

Locking files

After you open a file, you can lock it to prevent other users from submitting it before you do. The benefit of locking a file is that conflicts are prevented, but when you lock a file, you might prevent other team members from proceeding with their work on that file.

Also in this section:

Preventing multiple resolves by locking files	129
Preventing multiple checkouts	129

Preventing multiple resolves by locking files

Without file locking, there is no guarantee that the resolve process ever ends. The following scenario demonstrates the problem:

1. Bruno opens file for edit.
 2. Gale opens the same file in her client for edit.
 3. Bruno and Gale both edit their client workspace versions of the file.
 4. Bruno submits a changelist containing that file, and his submit succeeds.
 5. Gale submits a changelist with her version of the file; her submit fails because of file conflicts with the new depot's file.
 6. Gale starts a resolve.
 7. Bruno edits and submits a new version of the same file.
 8. Gale finishes the resolve and attempts to submit; the submit fails and must now be merged with Bruno's latest file.
- ...and so on.

To prevent such problems, you can lock files, as follows.

1. Before scheduling a resolve, lock the file.
2. Sync the file (to schedule a resolve).
3. Resolve the file.
4. Submit the file.
5. Helix server automatically unlocks the file after successful changelist submission.

To list open locked files on UNIX, issue the following command:

```
$ p4 opened | grep "*locked*"
```

Preventing multiple checkouts

To ensure that only one user at a time can work on the file, use the `+l` (exclusive-open) file type modifier. For example:

```
$ p4 reopen -t binary+l file
```

Although exclusive locking prevents concurrent development, for some file types (binary files), merging and resolving are not meaningful, so you can prevent conflicts by preventing multiple users from working on the file simultaneously.

Your Helix server administrator can use the `p4 typemap` command to ensure that all files of a specified type (for instance, `//depot/.../*.gif` for all `.gif` files) can only be opened by one user at a time. See the [Helix Core P4 Command Reference](#).

The difference between `p4 lock` and `+1` is that `p4 lock` allows anyone to open a file for edit, but only the person who locked the file can submit it. By contrast, a file of type `+1` prevents more than one user from opening the file.

Security

For security purposes, your Helix server administrator can configure the Helix server to require SSL-encrypted connections, user passwords, and to limit the length of time for which your login ticket is valid.

Note

Let your administrator know that Helix Core supports:

- integration with an identity provider through Helix Authentication Service, which is documented at [Helix Authentication Service Administrator Guide](#).
- multi-factor authentication, which is documented in "Helix Core Server Administrator Guide", in the chapter on "Securing the server", which has a section on [Multi-factor authentication](#).

SSL-encrypted connections	131
Connecting to services that require plaintext connections	133
Passwords	133
Setting passwords	133
Using your password	134
Connection time limits	134
Logging in and logging out	135
Working on multiple computers	135

SSL-encrypted connections

If your installation requires SSL, make sure your **P4PORT** is of the form **ssl:hostname:port**. If you attempt to communicate in plaintext with an SSL-enabled Helix server, the following error message is displayed:

```
Failed client connect, server using SSL.  
Client must add SSL protocol prefix to P4PORT.
```

Set **P4PORT** to **ssl:hostname:port**, and attempt to reconnect to the server.

The first time you establish an encrypted connection with an SSL-enabled server, you are prompted to verify the server's fingerprint:

```
The authenticity of '10.0.0.2:1818' can't be established,  
this may be your first attempt to connect to this P4PORT.  
The fingerprint for the key sent to your client is  
CA:BE:5B:77:14:1B:2E:97:F0:5F:31:6E:33:6F:0E:1A:E9:DA:EF:E2
```

Your administrator can confirm whether the displayed fingerprint is correct or not. If (and only if) the fingerprint is correct, use the `p4 trust` command to add it to your `P4TRUST` file. If `P4TRUST` is unset, this file is assumed to be `.p4trust` in your home directory:

```
$ p4 trust
The fingerprint of the server of your P4PORT setting
'ssl:example.com:1818' (10.0.0.2:1818) is not known.
That fingerprint is
CA:BE:5B:77:14:1B:2E:97:F0:5F:31:6E:33:6F:0E:1A:E9:DA:EF:E2
Are you sure you want to establish trust (yes/no)?
Added trust for P4PORT 'ssl:example.com:1818' (10.0.0.2:1818)
```

If the fingerprint is accurate, enter `yes` to trust this server. You can also install a fingerprint directly into your trust file from the command line. Run:

```
$ p4 trust -p ssl:hostname:port -i fingerprint
```

where `ssl:hostname:port` corresponds to your `P4PORT` setting, and `fingerprint` corresponds to a fingerprint that your administrator has verified.

From this point forward, any SSL connection to `ssl:example.com:1818` is trusted, so long as the server at `example.com:1818` continues to report a fingerprint that matches the one recorded in your `P4TRUST` file.

If the Helix server ever reports a different fingerprint than the one that you have trusted, the following error message is displayed:

```
***** WARNING P4PORT IDENTIFICATION HAS CHANGED! *****
It is possible that someone is intercepting your connection
to the Perforce P4PORT '10.0.50.39:1667'
If this is not a scheduled key change, then you should contact
your Perforce administrator.
The fingerprint for the mismatched key sent to your client is
18:FC:4F:C3:2E:FA:7A:AE:BC:74:58:2F:FC:F5:87:7C:BE:C0:2D:B5
To allow connection use the 'p4 trust' command.
```

This error message indicates that the server's fingerprint has changed from one that you stored in your `P4TRUST` file and indicates that the server's SSL credentials have changed.

Although the change to the fingerprint may be legitimate (for example, your administrator controls the length of time for which your server's SSL credentials remain valid, and your server's credentials may have expired), it can also indicate the presence of a security risk.

Warning

If you see this error message, and your Helix server administrator has not notified you of a change to your server's key and certificate pair, it is imperative that you *independently* verify the accuracy of the reported fingerprint.

Unless you can independently confirm the veracity of the new fingerprint (by some out-of-band means ranging from the company's intranet site, or by personally contacting your administrator), do not trust the changed fingerprint.

Also in this section:

[Connecting to services that require plaintext connections](#) 133

Connecting to services that require plaintext connections

If your Helix server installation requires plaintext (in order to support older Helix server applications), set **P4PORT** to `tcp:hostname:port`. If you attempt to use SSL to connect to a service that expects plaintext connections, the following error message is displayed:

```
Perforce client error:
```

```
SSL connect to ssl:_host_:_port_ failed (Connection reset by peer).
```

```
Remove SSL protocol prefix from P4PORT.
```

Set **P4PORT** to `tcp:hostname:port` (or, if you are using applications at release 2011.1 or earlier, set **P4PORT** to `hostname:port`), and attempt to reconnect to the service.

Passwords

Depending on the security level at which your Helix server installation is running, you might need to log in to Helix server before you can run Helix server commands. Without passwords, any user can assume the identity of any other Helix server user by setting **P4USER** to a different user name or specifying the `-u` option when you issue a **p4** command. To improve security, use passwords.

Also in this section:

[Setting passwords](#) 133
[Using your password](#) 134

Setting passwords

To create a password for your Helix server user, issue the `p4 passwd` command.

Passwords may be up to 1,024 characters in length. Your system administrator can configure Helix server to require “strong” passwords, the minimum length of a password, and if you have been assigned a default password, your administrator can further require that you change your password before you first use Helix server.

By default, the Helix server defines a password as strong if it is at least eight characters long and contains at least two of the following:

- Uppercase letters
- Lowercase letters
- Non-alphabetic characters

In an environment with a minimum password length of eight characters, for example, `a1b2c3d4`, `A1B2C3D4`, `aBcDeFgH` would be considered strong passwords.

To reset or remove a password (without knowing the password), Helix server superuser privilege is required. If you need to have your password reset, contact your Helix server administrator. See the *Helix Core Server Administrator Guide* for details.

Using your password

If your Helix server user has a password set, you must use it when you issue `p4` commands. To use the password, you can:

- Log into Helix server by issuing the `p4 login` command, before issuing other commands.
- Set `P4PASSWD` to your password, either in the environment or in a config file.
- Specify the `-P password` option when you issue `p4` commands (for instance, `p4 -P mypassword submit`).
- Windows or OS X: store your password by using the `p4 set -s` command. Not advised for sites where security is high. Helix server administrators can disable this feature.

Connection time limits

Your Helix server administrator can configure the Helix server to enforce time limits for users. Helix server uses ticket-based authentication to enforce time limits. Because ticket-based authentication does not rely on environment variables or command-line options, it is more secure than password-based authentication.

Tickets are stored in a file in your home directory. After you have logged in, your ticket is valid for a limited period of time (by default, 12 hours).

Also in this section:

[Logging in and logging out](#)135

Logging in and logging out

If time limits are in effect at your site, you must issue the `p4 login` command to obtain a ticket. Enter your password when prompted. If you log in successfully, a ticket is created for you in the ticket file in your home directory, and you are not prompted to log in again until either your ticket expires or you log out by issuing the `p4 logout` command.

To see how much time remains before your login expires, issue the following command:

```
$ p4 login -s
```

If your ticket is valid, the length of time remaining is displayed. To extend a ticket's lifespan, use `p4 login` while already logged in. Your ticket's lifespan is extended by 1/3 of its initial timeout setting, subject to a maximum of your ticket's initial timeout setting.

To log out of Helix server, issue the following command:

```
$ p4 logout
```

Working on multiple computers

By default, your ticket is valid only for the IP address of the computer from which you logged in. If you use Helix server from multiple computers that share a home directory (typical in many UNIX environments), log in with:

```
$ p4 login -a
```

Using `p4 login -a` creates a ticket in your home directory that is valid from all IP addresses, enabling you to remain logged into Helix server from more than one computer.

To log out from all computers simultaneously, issue the following command:

```
$ p4 logout -a
```

For more information about the `p4 login` and `p4 logout` commands, see the [Helix Core P4 Command Reference](#).

Labels

A Helix server label is a set of tagged file revisions. For example, you might want to tag the file revisions that compose a particular release with the label `release2.0.1`. You can use labels to:

- Keep track of all the file revisions contained in a particular release of software.
- Distribute a particular set of file revisions to other users. For example, a standard configuration.
- Populate a clean build workspace.
- Specify a set of file revisions to be branched for development purposes.
- Sync the revisions as a group to a client workspace.

Labels and changelist numbers differ:

Label	Changelist
A label can refer to any set of file revisions. If you need to refer to a group of file revisions from different points in time, use a label.	A changelist number refers to the contents of all the files in the depot at the time the changelist was submitted. If there is a point in time at which the files are consistent for your purposes, use a changelist number.
You can change the contents of a label.	You cannot change the contents of a submitted changelist.
You can assign your own names to labels.	Helix server assigns each changelist number.

There are two types of labels: static and automatic. See "[Static versus automatic labels](#)" on page 140 for a discussion of their differences.

Tagging files with a label

To tag a set of file revisions (in addition to any revisions that have already been tagged), use `p4 tag`, specifying a label name and the desired file revisions.

For example, to tag the head revisions of files that reside under `//JamCode/release/jam/2.1/src/` with the label `jam-2.1.0`, issue the following command:

```
$ p4 tag -l jam-2.1.0 //JamCode/release/jam/2.1/src/...
```

To tag revisions other than the head revision, specify a changelist number in the file pattern:

```
$ p4 tag -l jam-2.1.0 //JamCode/release/jam/2.1/src/...@1234
```

Only one revision of a given file can be tagged with a given label, but the same file revision can be tagged by multiple labels.

Untagging files

You can untag revisions with:

```
$ p4 tag -d -l labelname filepattern
```

This command removes the association between the specified label and the file revisions tagged by it. For example, if you have tagged all revisions under `//JamCode/release/jam/2.1/src/...` with `jam-2.1.0`, you can untag only the header files with:

```
$ p4 tag -d -l jam-2.1.0 //JamCode/release/jam/2.1/src/*.h
```

Previewing tagging results

You can preview the results of `p4 tag` with `p4 tag -n`. This command lists the revisions that would be tagged, untagged, or re-tagged without actually performing the operation.

Listing files tagged by a label

To list the revisions tagged with *labelname*, use `p4 files`, specifying the label name as follows:

```
$ p4 files @labelname
```

All revisions tagged with *labelname* are listed, with their file type, change action, and changelist number. (This command is equivalent to `p4 files //...@labelname`).

Listing labels that have been applied to files

To list all labels that have been applied to files, use the `p4 labels` command:

```
p4 labels filepattern
```

Using a label to specify file revisions

You can use a label name anywhere you can refer to files by revision (`#1`, `#head`), changelist number (`@7381`), or date (`@2017/08/29`).

If you omit file arguments when you issue the `p4 sync @labelname` command, all files in the workspace view that are tagged by the label are synced to the revision specified in the label. All files in the workspace that do not have revisions tagged by the label are deleted from the workspace. Open files or files not under Helix server control are unaffected. This command is equivalent to `p4 sync //...@labelname`.

If you specify file arguments when you issue the `p4 sync` command (`p4 sync files@labelname`), files that are in your workspace and tagged by the label are synced to the tagged revision.

Example Retrieving files tagged by a label into a client workspace

To retrieve the files tagged by Bruno's `jam-2.1.0` label into his client workspace, Bruno issues the following command:

```
$ p4 sync @ jam-2.1.0
```

and sees:

```
//JamCode/dev/jam/Build.com#5 - updating c:\bruno_
ws\dev\jam\Build.com
//JamCode/dev/jam/command.c#5 - updating c:\bruno_
ws\dev\jam\command.c
//JamCode/dev/jam/command.h#3 - added as c:\bruno_
ws\dev\jam\command.h
//JamCode/dev/jam/compile.c#12 - updating c:\bruno_
ws\dev\jam\compile.c
//JamCode/dev/jam/compile.h#2 - updating c:\bruno_
ws\dev\jam\compile.h
...
```

Deleting labels

To delete a label, use the following command:

```
$ p4 label -d labelname
```

Note

Only one revision of a given file can be tagged with a given label, but the same file revision can be tagged by multiple labels.

Creating a label for future use

To create a label without tagging any file revisions, issue the `p4 label labelname` command. This command displays a form in which you describe and specify the label. After you have created a label, you can use `p4 tag` or `p4 labelsync` to apply the label to file revisions.

Label names cannot be the same as client workspace, branch, or depot names.

For example, to create `jam-2.1.0`, issue the following command:

```
$ p4 label jam-2.1.0
```

The following form is displayed:

```
Label:  jam-2.1.0
Update: 2011/03/07 13:07:39
Access: 2011/03/07 13:13:35
Owner:  bruno
Description:
    Created by bruno.
Options:  unlocked noautoreload
View:
    //depot/...
```

Enter a description for the label and save the form. (You do not need to change the `View:` field.)

After you create the label, you are able to use the `p4 tag` and `p4 labelsync` commands to apply the label to file revisions.

Restricting files that can be tagged

The `View:` field in the `p4 label` form limits the files that can be tagged with a label. The default label view includes the entire depot (`//depot/...`). To prevent yourself from inadvertently tagging every file in your depot, set the label's `View:` field to the files and directories to be taggable, using depot syntax.

Example Using a label view to control which files can be tagged

Bruno wants to tag the revisions of source code in the release 2.1 branch, which he knows can be successfully compiled. He types `p4 label jam-2.1.0` and uses the label's `View:` field to restrict the scope of the label as follows:

```
Label:  jam-2.1.0
Update: 2018/03/27 13:07:39
Access: 2018/03/27 13:13:35
Owner:  bruno
```

```

Description:
    Created by bruno.
Options:    unlocked noautoreload
View:
    //JamCode/release/jam/2.1/src/...

```

This label can tag only files in the release 2.1 source code directory.

Static versus automatic labels

There are two types of labels:

static	automatic
<p>Use static labels with the <code>p4 tag</code> and <code>p4 labelsync</code> commands.</p> <p><code>p4 tag</code> allows you to add and delete file revisions from a label.</p> <p><code>p4 labelsync</code> allows you to use the named label to apply the current contents of the client to the label.</p>	<p>Automatic labels perform much better than static labels when synced because they are aliases for changelists.</p> <p>Automatic labels using a changelist revision do not require storing each file revision, which greatly reduces the amount of data that must be stored and scanned when referencing the label.</p> <p>Note that when executing the command <code>p4 labels <filespec></code>, automatic labels do not display.</p>

Static labels

You can use static labels to archive the state of your client workspace (meaning the currently synced file revisions) by issuing the `p4 labelsync` command. The label you specify must have the same view as your client workspace.

For example, to record the configuration of your current client workspace using the existing `ws_config` label, use the following command:

```
$ p4 labelsync -l ws_config
```

All file revisions that are synced to your current workspace and visible through both the workspace view and the label view (if any) are tagged with the `ws_config` label. Files that were previously tagged with `ws_config`, then subsequently removed from your workspace (`p4 sync #none`), are untagged.

To sync the files tagged by the `ws_config` label (thereby recreating the workspace configuration):

```
$ p4 sync @ws_config
```

Note

You can control how static labels are stored using the `autoreload` or `noautoreload` options:

- `autoreload` stores the labels in the unload depot. This storage option can improve performance on sites that make heavy use of labels.
- `noautoreload` stores the labels in the `db.label` table.

These storage options do not affect automatic labels.

`p4 tag` allows you to specify any revision of any file, and add that revision to an existing label or create a new label if the label does not exist.

`p4 labelsync` allows you to use the named label to tag the current contents of the client.

When syncing static labels, the performance is the same regardless of how they are created.

Automatic labels

Automatic labels refer to the revisions provided in the `View:` and `Revision:` fields of the label specification. To create an automatic label, fill in the `Revision:` field of the `p4 label` spec with a revision specifier. When you sync a workspace to an automatic label, the contents of the `Revision:` field are applied to every file in the `View:` field.

Example Using an automatic label as an alias for a changelist number

Bruno is running a nightly build process, and has successfully built a product as of changelist 1234. Rather than having to remember the specific changelist for every night's build, he types `p4 label nightly20111201` and uses the label's `Revision:` field to automatically tag all files as of changelist 1234 with the `nightly20111201` label:

```
Label:  nightly20111201
Owner:  bruno
Description:
    Nightly build process.
Options:  unlocked noautoreload
View:
    //depot/...
Revision:
    @1234
```

The advantage to this approach is that it is highly amenable to scripting, takes up very little space in the label table, and provides a way to easily refer to a nightly build without remembering which changelist number was associated with the night's build process.

Example Referring specifically to the set of files submitted in a single changelist

A bug was fixed by means of changelist 1238, and requires a patch label that refers to only those files associated with the fix. Bruno types `p4 label patch20111201` and uses the label's **Revision:** field to automatically tag only those files submitted in changelist 1238 with the `patch20111201` label:

```
Label: patch20111201
Owner: bruno
Description:
    Patch to 2011/12/01 nightly build.
Options:    unlocked noautoreload
View:
    //depot/...
Revision:
    @1238,1238
```

This automatic label refers only to those files submitted in changelist 1238.

Example Referring to the first revision of every file over multiple changelists

You can use revision specifiers other than changelist specifiers. In this example, Bruno specifies to the first revision (#1) of every file in a branch. Depending on how the branch was populated, these files could have been created through multiple changelists over a long period of time:

```
Label: first2.2
Owner: bruno
Description:
    The first revision in the 2.2 branch
Options:    unlocked noautoreload
View:
    //JamCode/release/jam/2.2/src/...
Revision:
    "#1"
```

Because Helix server forms use the `#` character as a comment indicator, Bruno has placed quotation marks around the `#` to ensure that it is parsed as a revision specifier.

Also in this section:

[Automatic labels: superior performance](#) 143

Automatic labels: superior performance

Automatic labels perform much better than static labels when synced because they are aliases for changelists.

- Static labels must store information for every file revision associated with the label. Sites using a large number of static labels with a large number of revisions have a very large `db.label` table.
- Automatic labels using a changelist revision do not require storing each file revision, which greatly reduces the amount of data that must be stored and scanned when referencing the label.

When using automatic labels containing both `View:` and `Revision:` fields, use of the automatic labels to represent a revision ranges might not produce the same results when using the equivalent changelist revision range. You can make an automatic label behave exactly like its revision specifier by leaving the `View:` field blank. Without this field, the automatic label is considered a pure alias and is processed exactly like the revision specification.

Tip

A changelist number can apply to more files than the number of files submitted by the changelist.

For example, putting `@1234` in the `Revision:` field and `//depot/...` in the `View:` field of a label spec creates a label that is an alias for changelist `1234` for all files within `depot` at the time the change was submitted, even if only one file revision was submitted with the change.

Changelist numbers increment in chronological order, and automatic labels can be used as fixed points for any file or set of files in your depot.

Preventing inadvertent tagging and untagging of files

To tag the files that are in your client workspace and label view (if set) and untag all other files, issue the `p4 labelsync` command with no arguments. To prevent the inadvertent tagging and untagging of files, issue the `p4 label labelname` command and lock the label by setting the `Options:` field of the label form to `Locked`. To prevent other users from unlocking the label, set the `Owner:` field. For details about Helix server privileges, see the [Helix Core Server Administrator Guide](#).

Using labels on edge servers

You can use the Helix Core server in a multi-server environment using central and edge servers. With a multi-server Helix server architecture, users typically connect to an edge server and execute commands just as they would with a *classic* Helix server. For more information, see [Helix Core Server Administrator Guide](#).

When connected to an edge server, the commands `p4 label`, `p4 labelsync`, and `p4 tag` operate on labels local to the edge server. Global labels can be manipulated by using the `-g` option. For details, see the [Helix Core P4 Command Reference](#).

Note

Using the `-g` option with `p4 labelsync` only works with a global client. To manipulate a global label, use `p4 tag`.

Using labels with Git

If you are using Git with Helix server, and you want to support build systems that need to build from multiple repos not all of which are at the same branch, tag, or commit (SHA), create a label specification in which the `Revision:` field is set to `"#head"`:

```
# A Perforce Label Specification.
Label:      mylabel
Update:     2017/08/08 15:23:08
Access:     2012/01/23 16:16:17
Owner:      bruno
Description:
    Created by bruno.
Options:    unlocked noautoreload
Revision:   "#head"
View:
    //repo/linux/projects/...@master
    //repo/linux/projects/drivers/...@dev-1
    //repo/linux/projects/forms/...@4759B19D1EB8B706E71D54AD168AA
```

For more information about using Git with Helix server, see [Helix4Git Administration](#).

Jobs

A *job* is a numbered (or named) work request managed by Helix server. Helix server jobs enable you to track the status of bugs and enhancement requests and associate them with changelists that implement fixes and enhancements. You can search for jobs based on the contents of fields, the date the job was entered or last modified, and many other criteria.

Your Helix server administrator can customize the job specification for your site's requirements. For details on modifying the job specification, see the *Helix Core Server Administrator Guide*.

To integrate Helix server with your in-house defect tracking system, or to develop an integration with a third-party defect tracking system, use P4DTG, the Helix Defect Tracking Gateway. P4DTG is an integrated platform that includes both a graphical configuration editor and a replication engine. For more information, see <https://www.perforce.com/plugins-integrations/defect-tracking-gateway>

Creating, editing, and deleting a job	145
Searching jobs	146
Searching job text	147
Searching specific fields	147
Using comparison operators	148
Searching date fields	149
Fixing jobs	149
Linking automatically	150
Linking manually	150
Linking jobs to changelists	151

Creating, editing, and deleting a job

To create a job using Helix server's default job-naming scheme, issue the `p4 job` command. To assign a name to a new job (or edit an existing job), issue the `p4 job jobname` command.

Example Creating a job

Gale discovers a problem with Jam, so she creates a job by issuing the `p4 job` command and describes it as follows:

```
Job:      job000006

Status:   open

User:     gale

Date:     2011/11/14 17:12:21
```

Description:

MAXLINE can't account for expanded cmd buffer size.

The following table describes the fields in the default job specification:

Field Name	Description	Default
Job	The name of the job (white space is not allowed). By default, Helix server assigns job names using a numbering scheme (jobnnnnnn).	Last job number +1
Status	<ul style="list-style-type: none"> ▪ open: job has not yet been fixed. ▪ closed: job has been completed. ▪ suspended: job is not currently being worked on. 	open
User	The user to whom the job is assigned, usually the person assigned to fix this particular problem.	Helix server user name of the job creator.
Date	The date the job was last modified.	Updated by Helix server when you save the job.
Description	Describes the work being requested, for example a bug description or request for enhancement.	None. You must enter a description.

To edit existing jobs, specify the job name when you issue the **p4 job** command: **p4 job jobname**. Enter your changes in the job form, save the form and exit.

To delete a job, issue the **p4 job -d jobname** command.

Searching jobs

To search Helix server jobs, issue the **p4 jobs -e jobview** command, where *jobview* specifies search expressions described in the sections listed below. For more details, issue the **p4 help jobview** command.

Also in this section:

Searching job text	147
Searching specific fields	147
Using comparison operators	148
Searching date fields	149

Searching job text

You can use the expression `'word1 word2 ... wordN'` to find jobs that contain all of *word1* through *wordN* in any field (excluding date fields). Use single quotes on UNIX and double quotes on Windows.

When searching jobs, note the following restrictions:

- When you specify multiple words separated by whitespace, Helix server searches for jobs that contain *all* the words specified. To find jobs that contain *any* of the terms, separate the terms with the pipe (`|`) character.
- Field names and text comparisons in expressions are not case-sensitive.
- Only alphanumeric text and punctuation can appear in an expression. To match the following characters, which are used by Helix server as logical operators, precede them with a backslash: `=^&|()<>`.
- You cannot search for phrases, only individual words.

Example Searching jobs for specific words

Bruno wants to find all jobs that contain the words `filter`, `file`, and `mailbox`. He types:

```
$ p4 jobs -e 'filter file mailbox'
```

Example Finding jobs that contain any of a set of words in any field

Bruno wants to find jobs that contain any of the words `filter`, `file` or `mailbox`. He types:

```
$ p4 jobs -e 'filter|file|mailbox'
```

You can use the `*` wildcard to match one or more characters. For example, the expression `fieldname=string*` matches `string`, `strings`, `stringbuffer`, and so on.

To search for words that contain wildcards, precede the wildcard with a backslash in the command. For instance, to search for `*string` (perhaps in reference to `char *string`), issue the following command:

```
$ p4 jobs -e '\*string'
```

Searching specific fields

To search based on the values in a specific field, specify `field=value`.

Example Finding jobs that contain words in specific fields

Bruno wants to find all open jobs related to filtering. He types:

```
$ p4 jobs -e 'Status=open User=bruno filter.c'
```

This command finds all jobs with a **Status:** of **open**, a **User:** of **bruno**, and the word **filter.c** in any non-date field.

To find fields that do not contain a specified expression, precede it with **^**, which is the NOT operator. The NOT operator **^** can be used only directly after an AND expression (space or **&**). For example, **p4 jobs -e '^user=bruno'** is not valid. To get around this restriction, use the ***** wildcard to add a search term before the **^** term; for example: **p4 jobs -e 'job=* ^user=bruno'** returns all jobs not owned by Bruno.

Example Excluding jobs that contain specified values in a field

Bruno wants to find all open jobs he does not own that involve filtering. He types:

```
$ p4 jobs -e 'status=open ^user=bruno filter'
```

This command displays all open jobs that Bruno does not own that contain the word **filter**.

Using comparison operators

The following comparison operators are available: **=**, **>**, **<**, **>=**, **<=**, and **^** for Boolean NOT.

The behavior of these operators depends upon the type of the field in the expression. The following table describes the field types and how they can be searched:

Field Type	Description	Notes
word	A single word	<p>The equality operator (=) matches the value in the word field exactly.</p> <p>The relational operators perform comparisons in ASCII order.</p>
text	A block of text entered on the lines beneath the field name.	<p>The equality operator (=) matches the job if the value is found anywhere in the specified field.</p> <p>The relational operators are of limited use here, because they'll match the job if <i>any</i> word in the specified field matches the provided value. For example, if a job has a text field ShortDescription: that contains only the phrase gui bug, and the expression is 'ShortDesc<filter', the job will match the expression, because bug<filter.</p>
line	A single line of text entered on the same line as the field name.	Same as text .

Field Type	Description	Notes
<code>select</code>	One of a set of values. For example, job status can be <code>open</code> , <code>suspended</code> , or <code>closed</code> .	The equality operator (<code>=</code>) matches a job if the value in the field is the specified word. Relational operators perform comparisons in ASCII order.
<code>date</code>	A date and optionally a time. For example, <code>2011/07/15:13:21:40</code> .	Dates are matched chronologically. If a time is not specified, the operators <code>=</code> , <code><=</code> , and <code>>=</code> match the whole day.
<code>bulk</code>	Like <code>text</code> , but not indexed for searching.	These fields are not searchable with <code>p4 jobs -e</code> .

If you're not sure of a field's type, issue the `p4 jobspec -o command`, which displays your job specification. The field called `Fields:` lists the job fields' names and data types.

Searching date fields

To search date fields, specify the date using the format `yyyy/mm/dd` or `yyyy/mm/dd:hh:mm:ss`. If you omit time, the equality operator (`=`) matches the entire day.

Example Using dates within expressions

Bruno wants to view all jobs modified on July 13, 2011. He enters:

```
$ p4 jobs -e 'ModifiedDate=2011/07/13'
```

Fixing jobs

To fix a job, you link it to a changelist and submit the changelist. Helix server automatically changes the value of a job's status field to `closed` when the changelist is submitted.

Jobs can be linked to changelists in one of three ways:

- By setting the `JobView:` field in the `p4 user` form to an expression that matches the job.
- With the `p4 fix` command.
- By editing the `p4 submit` form.

You can modify job status directly by editing the job, but if you close a job manually, there's no association with the changelist that fixed the job. If you have altered your site's job specification by deleting the `Status:` field, jobs can still be linked to changelists, but status cannot be changed when the changelist is submitted. (In most cases, this is not a desired form of operation.) See the chapter on editing job specifications in the [Helix Core Server Administrator Guide](#) for more details.

To remove jobs from a changelist, issue the `p4 fix -d` command.

Also in this section:

Linking automatically	150
Linking manually	150
Linking jobs to changelists	151

Linking automatically

You can modify your Helix server user specification to automatically attach open jobs to any changelists you create. To set up automatic inclusion, issue the `p4 user` command and set the `JobView:` field value to a valid expression that locates the jobs you want attached.

Example Automatically linking jobs to changelists

Bruno wants to see all open jobs that he owns in all changelists he creates. He types `p4 user` and adds the `JobView:` field:

```
User:      bruno
Update:    2011/06/02 13:11:57
Access:    2011/06/03 20:11:07
JobView:   user=bruno&status=open
```

All of Bruno's open jobs now are automatically attached to his default changelist. When he submits changelists, he must be sure to delete jobs that aren't fixed by the changelist he is submitting.

Linking manually

To link a job to a changelist manually, issue the `p4 fix -c changenum jobname` command. If the changelist has already been submitted, the value of the job's `Status:` field is changed to `closed`. Otherwise, the status is not changed.

Example Manually linking jobs to changelists.

You can use `p4 fix` to link a changelist to a job owned by another user.

Sarah has just submitted a job called `options-bug` to Bruno, but the bug has already been fixed in Bruno's previously submitted changelist 18. Bruno links the job to the changelist by typing:

```
$ p4 fix -c 18 options-bug
```

Because changelist 18 has already been submitted, the job's status is changed to `closed`.

Linking jobs to changelists

To link jobs to changelists when submitting or editing the changelist, enter the job names in the **Jobs :** field of the changelist specification. When you submit the changelist, the job is (by default) closed.

To unlink a job from a pending changelist, edit the changelist and delete its name from the **Jobs :** field.

To unlink a job from a submitted changelist, issue the `p4 fix -d -c changenumberjobname` command.

Scripting and reporting

This chapter provides details about using `p4` commands in scripts and for reporting purposes. For a full description of any particular command, see the *Helix Core P4 Command Reference*, or issue the `p4 help` command.

Common options used in scripting and reporting	152
Scripting with Helix server forms	153
File reporting	154
Displaying file status	155
Displaying file revision history	156
Listing open files	156
Displaying file locations	157
Displaying file contents	157
Displaying annotations (details about changes to file contents)	158
Monitoring changes to files	159
Changelist reporting	159
Listing changelists	159
Listing files and jobs affected by changelists	160
Label reporting	161
Branch and integration reporting	161
Job reporting	162
Listing jobs	162
Listing jobs fixed by changelists	162
System configuration reporting	163
Displaying users	163
Displaying workspaces	164
Listing depots	164
Sample script	164

Common options used in scripting and reporting

The command-line options described below enable you to specify settings on the command line and in scripts. For full details, refer to the description of global options in the *Helix Core P4 Command Reference*.

Option	Description
<code>-b</code> <code>batchsize</code>	Specify a batch size (number of arguments) to use when processing a command from <code>-x argfile</code> . By default, 128 arguments are read at a time.
<code>-c client_</code> <code>workspace</code>	Specifies the client workspace name.

Option	Description
<code>-G</code>	Causes all output (and batch input for form commands with <code>-i</code>) to be formatted as marshaled Python dictionary objects.
<code>-p protocol:host:port</code>	Specifies the host and port number of the Helix server, as well as the protocol used to connect.
<code>-P password</code>	Specifies the user password if any. If you prefer your script to log in before running commands (instead of specifying the password every time a command is issued), use the <code>p4 login</code> command. For example: <pre>\$ echo 'mypassword' p4 login</pre>
<code>-s</code>	Prepends a descriptive field (for example, <code>text:</code> , <code>info:</code> , <code>error:</code> , <code>exit:</code>) to each line of output produced by a Helix server command.
<code>-u user</code>	Specifies the Helix server user name.
<code>-x argfile</code>	Reads arguments, one per line, from the specified file. If <code>argfile</code> is a single hyphen (<code>-</code>), then standard input is read.

Scripting with Helix server forms

If your scripts issue `p4` commands that require the user to fill in a form, such as the `p4 client` and `p4 submit` commands, use the `-o` option to write the form to standard output and the `-i` option to read the edited form from standard input.

For example, to create a job using a script on UNIX:

1. Write a blank job specification into a text file.

```
$ p4 job -o > temp1
```

2. Make the necessary changes to the job.

For example:

```
$ sed 's/<enter description here>/Crashes on exit./' temp1 >
temp2
```

3. Save the job.

```
$ p4 job -i < temp2
```

To accomplish the preceding without a temporary file, issue the following command:

```
$ p4 job -o | sed 's/<enter description here>/Crashes on exit./' | p4
job -i
```

The commands that display forms are:

- `p4 branch`
- `p4 change`
- `p4 client`
- `p4 job`
- `p4 label`
- `p4 submit` (use `p4 change -o` to create changelist, or `p4 submit -d "A changelist description"` to supply a description to the default changelist during changelist submission.)
- `p4 stream`
- `p4 user`

File reporting

The sections below describe commands that provide information about file status and location. The following table lists a few basic and highly-useful reporting commands:

To display this information	Use this command
File status, including file type, latest revision number, and other information	<code>p4 files</code>
File revisions from most recent to earliest	<code>p4 filelog</code>
Currently opened files	<code>p4 opened</code>
Preview of <code>p4 sync</code> results	<code>p4 sync -n</code>
Summarize a <code>p4 sync</code> preview, estimate network traffic	<code>p4 sync -N</code>
Currently synced files	<code>p4 have</code>
The contents of specified files	<code>p4 print</code>
The mapping of files' depot locations to the corresponding workspace locations.	<code>p4 where</code>
A list of files and full details about the files	<code>p4 fstat</code>

Also in this section:

[Displaying file status](#) 155

Displaying file revision history	156
Listing open files	156
Displaying file locations	157
Displaying file contents	157
Displaying annotations (details about changes to file contents)	158
Monitoring changes to files	159

Displaying file status

To display information about single revisions of files, issue the `p4 files` command. This command displays the locations of the files in the depot, the actions (`add`, `edit`, `delete`, and so on) performed on those files at the specified revisions, the changelists in which the specified file revisions were submitted, and the files' types. The following example shows typical output of the `p4 files` command:

```
//depot/README#5 - edit change 6 (text)
```

The `p4 files` command requires one or more *filespec* arguments. Regardless of whether you use local, client, or depot syntax to specify the filespec arguments, the `p4 file` command displays results using depot syntax. If you omit the revision number, information for the head revision is displayed. The output of `p4 files` includes deleted revisions.

The following table lists some common uses of the `p4 files` command:

To display the status of	Use this command
All files in the depot, regardless of your workspace view For depots containing numerous files, you can maximize performance by avoiding commands that refer to the entire depot (<code>//depot/...</code>) when not required. For best performance, specify only the directories and files of interest.	<code>p4 files</code> <code>//depot/...</code>
The files currently synced to the specified client workspace.	<code>p4 files</code> <code>@workspacename</code>
The files mapped by your workspace view.	<code>p4 files</code> <code>//</code> <code>workspacename</code> <code>/...</code>
Specified files in the current working directory	<code>p4 files</code> <code>filespec</code>
A specified file revision	<code>p4 files</code> <code>filespec#rev</code>

To display the status of	Use this command
Specified files at the time a changelist was submitted, regardless of whether the files were submitted in the changelist	<code>p4 files filespec @changenumber</code>
Files tagged with a specified label	<code>p4 files filespec @labelname</code>

Displaying file revision history

To display the revision history of a file, issue the `p4 filelog filespec` command. The following example shows how `p4 filelog` displays revision history:

```
$ p4 filelog //JamCode/dev/jam/jam.c
//JamCode/dev/jam/jam.c
... #35 change 627 edit on 2011/11/13 by earl@earl-dev-yew (text)
'Handle platform variants better'
... #34 change 598 edit on 2011/10/24 by raj@raj-althea (text)
'Reverse previous attempt at fix'
... ... branch into //JamCode/release/jam/2.2/src/jam.c#1
... #33 change 581 edit on 2011/10/03 by gale@gale-jam-oak (text)
'Version strings & release notes'
```

To display the entire description of each changelist, specify the `-l` option.

Listing open files

To list the files that are currently opened in a client workspace, issue the `p4 opened filespec` command. The following line is an example of the output displayed by the `p4 opened` command:

```
//JamCode/dev/jam/fileos2.c- edit default change (text)
```

The following table lists some common uses of the `p4 opened` command:

To list	Use this command
Opened files in the current workspace	<code>p4 opened</code>
Opened files in all client workspaces	<code>p4 opened -asp4 opened -a</code>
Files in a numbered pending changelist	<code>p4 opened -c changelist</code>
Files in the default changelist	<code>p4 opened -c default</code>

To list	Use this command
Whether a specific file is opened by you	<code>p4 opened filespec</code>
Whether a specific file is opened by anyone	<code>p4 opened -a filespec</code>

Displaying file locations

To display information about the locations of files, use the `p4 where`, `p4 have`, and `p4 sync -n` commands:

- To display the location of a file in depot, client, and local syntax, issue the `p4 where` command.
- To list the location and revisions of files that you last synced to your client workspace, issue the `p4 have` command.
- To see where files will be synced in your workspace, preview the sync by issuing the `p4 sync -n` command.

You can use these commands with or without *filespec* arguments.

The following table lists some useful location reporting commands:

To display	Use this command
The revision number of a file that you synced to your workspace	<code>p4 have filespec</code>
How a particular file in the depot maps to your workspace	<code>p4 where //depot/filespec</code>

Displaying file contents

To display the contents of a file in the depot, issue the `p4 print filespec` command. This command prints the contents of the file to standard output or to a specified output file, with a one-line banner that describes the file. To suppress the banner, specify the `-q` option. By default, the head revision is displayed, but you can specify a file revision.

To display the contents of files	Use this command
At the head revision	<code>p4 print filespec</code>
Without the banner	<code>p4 print -q filespec</code>
At a specified changelist number	<code>p4 print filespec@changenum</code>

Displaying annotations (details about changes to file contents)

To find out which file revisions or changelists affected lines in a text file, issue the `p4 annotate` command.

By default, `p4 annotate` displays the file line by line, with each line preceded by a revision number indicating the revision that made the change. To display changelist numbers instead of revision numbers, specify the `-c` option.

Example Using `p4 annotate` to display changes to a file

A file is added (`file.txt#1`) to the depot, containing the following lines:

```
This is a text file.
The second line has not been changed.
The third line has not been changed.
```

The third line is deleted and the second line edited so that `file.txt#2` reads:

```
This is a text file.
The second line is new.
```

The output of `p4 annotate` and `p4 annotate -c` look like this:

```
$ p4 annotate file.txt
//Acme/files/file.txt#3 - edit change 153 (text)
1: This is a text file.
2: The second line is new.
```

```
$ p4 annotate -c file.txt
//Acme/files/file.txt#3 - edit change 153 (text)
151: This is a text file.
152: The second line is new.
```

The first line of `file.txt` has been present since revision 1, which was submitted in changelist 151. The second line has been present since revision 2, which was submitted in changelist 152.

To show all lines (including deleted lines) in the file, use `p4 annotate -a` as follows:

```
$ p4 annotate -a file.txt
//Acme/files/file.txt#3 - edit change 12345 (text)
1-3: This is a text file.
1-1: The second line has not been changed.
```

```
1-1: The third line has not been changed.
2-3: The second line is new.
```

The first line of output shows that the first line of the file has been present for revisions 1 through 3. The next two lines of output show lines of `file.txt` present only in revision 1. The last line of output shows that the line added in revision 2 is still present in revision 3.

You can combine the `-a` and `-c` options to display all lines in the file and the changelist numbers (rather than the revision numbers) at which the lines existed.

Monitoring changes to files

The following table lists commands that display information about the status of files, changelists, and users:

To list	Use this command
The users who review specified files	<code>p4 reviews filespec</code>
The users who review files in a specified changelist	<code>p4 reviews -c changenum</code>
A specified user's email address	<code>p4 users username</code>

Changelist reporting

The `p4 changes` command lists changelists that meet search criteria, and the `p4 describe` command lists the files and jobs associated with a specified changelist.

Also in this section:

Listing changelists	159
Listing files and jobs affected by changelists	160

Listing changelists

To list changelists, issue the `p4 changes` command. By default, `p4 changes` displays one line for every public changelist known to the system, as well as for any restricted changelists to which you have access. The following table lists command-line options that you can use to filter the list.

To list changelists	Use this command
With the first 31 characters of the changelist descriptions	<code>p4 changes</code>

To list changelists	Use this command
With full descriptions	<code>p4 changes -l</code>
The last <i>n</i> changelists	<code>p4 changes -m n</code>
With a specified status	<code>p4 changes -s pending</code> <code>p4 changes -s submitted</code> <code>p4 changes -s shelved</code>
From a specified user	<code>p4 changes -u user</code>
From a specified workspace	<code>p4 changes -c workspace</code>
That affect specified files	<code>p4 changes filespec</code>
That affect specified files, including changelists that affect files that were later integrated with the named files	<code>p4 changes -i filespec</code>
That affect specified files, including only those changelists between revisions <i>m</i> and <i>n</i> of these files	<code>p4 changes filespec#m,#n</code>
That affect specified files at each revision between the revisions specified in labels <i>label1</i> and <i>label2</i>	<code>p4 changes filespec @label1,@label2</code>
Submitted between two dates	<code>p4 changes @date1,@date2</code>
Submitted on or after a specified date	<code>p4 changes @date1,@now</code>

Listing files and jobs affected by changelists

To list files and jobs affected by a specified changelist, along with the diffs of the changes, issue the `p4 describe` command. To suppress display of the diffs (for shorter output), specify the `-s` option. The following table lists some useful changelist reporting commands:

To list	Use this command
Files in a pending changelist	<code>p4 opened -c changenum</code>
Files submitted and jobs fixed by a particular changelist, including diffs	<code>p4 describe changenum</code>

To list	Use this command
Files submitted and jobs fixed by a particular changelist, suppressing diffs	<code>p4 describe -s changenum</code>
Files and jobs affected by a particular changelist, passing the context diff option to the underlying diff program	<code>p4 describe -dc changenum</code>
The state of particular files at a particular changelist, regardless of whether these files were affected by the changelist	<code>p4 files filespec @changenumber</code>

For more commands that report on jobs, see ["Job reporting" on the facing page](#).

Label reporting

To display information about labels, issue the `p4 labels` command. The following table lists some useful label reporting commands:

To list	Use this command
All labels, with creation date and owner	<code>p4 labels</code>
All labels containing a specific file revision (or range)	<code>p4 labels file#revrange</code>
Files tagged with a specified label	<code>p4 files @labelname</code>
A preview of the results of syncing to a label	<code>p4 sync -n @labelname</code>

Branch and integration reporting

The following table lists commonly used commands for branch and integration reporting:

To list	Use this command
All branch specifications	<code>p4 branches</code>
Files in a specified branch	<code>p4 files filespec</code>
The revisions of a specified file	<code>p4 filelog filespec</code>
The revisions of a specified file, recursively including revisions of the files from which it was branched	<code>p4 filelog -i filespec</code>
A preview of the results of a resolve	<code>p4 resolve [args] -n [filespec]</code>

To list	Use this command
Files that have been resolved but not yet submitted	<code>p4 resolved [filespec]</code>
Integrated, submitted files that match the <i>filespec</i> arguments	<code>p4 integrated filespec</code>
A preview of the results of an integration	<code>p4 integrate [args] -n [filespec]</code>

Job reporting

To list jobs, issue the `p4 jobs` command.

Also in this section:

Listing jobs	162
Listing jobs fixed by changelists	162

Listing jobs

The following table lists common job reporting commands:

To list	Use this command
All jobs	<code>p4 jobs</code>
All jobs, including full descriptions	<code>p4 jobs -l</code>
Jobs that meet search criteria (see "Searching jobs" on page 146 for details)	<code>p4 jobs -e jobview</code>
Jobs that were fixed by changelists that contain specific files	<code>p4 jobs filespec</code>
Jobs that were fixed by changelists that contain specific files, including changelists that contain files that were later integrated into the specified files	<code>p4 jobs -i filespec</code>

Listing jobs fixed by changelists

Any jobs that have been linked to a changelist with `p4 change`, `p4 submit`, or `p4 fix` are referred to as *fixed* (regardless of whether their status is `closed`). To list jobs that were fixed by changelists, issue the `p4 fixes` command.

The following table lists useful commands for reporting fixes:

To list	Use this command
all changelists linked to jobs	<code>p4 fixes</code>
all changelists linked to a specified job	<code>p4 fixes -j jobname</code>
all jobs linked to a specified changelist	<code>p4 fixes -c changenum</code>
all fixes associated with specified files	<code>p4 fixes filespec</code>
all fixes associated with specified files, including changelists that contain files that were later integrated with the specified files	<code>p4 fixes -i filespec</code>

System configuration reporting

The commands described in this section display Helix server users, client workspaces, and depots.

Displaying users	163
Displaying workspaces	164
Listing depots	164

Displaying users

The `p4 users` command displays the user name, an email address, the user's "real" name, and the date that Helix server was last accessed by that user, in the following format:

```
bruno <bruno@bruno_ws> (bruno) accessed 2011/03/07
dai <dai@dai_ws> (Dai Sato) accessed 2011/03/04
earl <earl@earl_ws> (Earl Ashby) accessed 2011/03/07
gale <gale@gale_ws> (Gale Beal) accessed 2011/06/03
hera <hera@hera_ws> (Hera Otis) accessed 2011/10/03
ines <ines@ines_ws> (Ines Rios) accessed 2011/02/02
jack <jack@submariner> (jack) accessed 2011/03/02
mei <mei@mei_ws> (Mei Chang) accessed 2011/11/14
ona <ona@ona_ws> (Ona Birch) accessed 2011/10/23
quinn <quinn@quinn_ws> (Quinn Cass) accessed 2011/01/27
```

```
raj <raj@ran_ws> (Raj Bai) accessed 2011/07/28
vera <vera@vera_ws> (Vera Cullen) accessed 2011/01/15
```

Displaying workspaces

To display information about client workspaces, issue the `p4 clients` command, which displays the client workspace name, the date the workspace was last updated, the workspace root, and the description of the workspace, in the following format:

```
Client bruno_ws 2011/03/07 root c:\bruno_ws ''
Client earl-dev-beech 2011/10/26 root /home/earl ''
Client earl-dev-guava 2011/09/08 root /usr/earl/development ''
Client earl-dev-yew 2011/11/19 root /tmp ''
Client earl-win-buckeye 2011/03/21 root c:\src ''
Client earl-qnx-elm 2011/01/17 root /src ''
Client earl-tupelo 2011/01/05 root /usr/earl ''
```

Listing depots

To list depots, issue the `p4 depots` command. This command lists the depot's name, its creation date, its type (`local`, `remote`, `archive`, `spec`, or `stream`), its host name or IP address (if `remote`), the mapping to the local depot, and the system administrator's description of the depot.

For details about defining multiple depots on a single Helix server installation, see the [Helix Core Server Administrator Guide](#).

Sample script

The following sample script parses the output of the `p4 fstat` command to report files that are opened where the head revision is not in the client workspace (a potential problem):

Example

```
#!/bin/sh
# Usage: opened-not-head.sh files
# Displays files that are open when the head revision is not
# on the client workspace

echo=echo
exit=exit
```

```
p4=p4
sed=sed

if [ $# -ne 1 ]
then
    $echo "Usage: $0 files"
    $exit 1
fi

$p4 fstat -Ro $1 | while read line
do
    name=`$echo $line | $sed 's/^\[\. \]\+\([^\ ]\+\) .*$/\1/'`
    value=`$echo $line | $sed 's/^\[\. \]\+ \[^\ ]\+ \(.*\)$/1/'`

    if [ "$name" = "depotFile" ]
    then
        depotFile=$value

    elif [ "$name" = "headRev" ]
    then
        headRev=$value

    elif [ "$name" = "haveRev" ]
    then
        haveRev=$value

        if [ $headRev != $haveRev ]
        then
            $echo $depotFile
        fi
    fi
done
```

Helix server file types

Helix server supports a set of file types that enable it to determine how files are stored by the Helix server and whether the file can be diffed. When you add a file, Helix server attempts to determine the type of the file automatically: Helix server first determines whether the file is a regular file or a symbolic link, and then examines the first part of the file to determine whether it's **text** or **binary**. If any non-text characters are found, the file is assumed to be **binary**; otherwise, the file is assumed to be **text**. (Files in Unicode environments are detected differently; see "[Helix server file type detection and Unicode](#)" on page 171.

To determine the type of a file under Helix server control, issue the **p4 opened** or **p4 files** command. To change the Helix server file type, specify the **-tfiletype** option. For details about changing file type, refer to the descriptions of **p4 add**, **p4 edit**, and **p4 reopen** in the [Helix Core P4 Command Reference](#).

Helix server supports the following file types:

Keyword	Description	Comments	Stored as
binary	Non-text file	Synced as binary files in the workspace. Stored compressed within the depot.	full file, compressed
symlink	Symbolic link	Helix server applications on UNIX, OS X, recent versions of Windows treat these files as symbolic links. On other platforms, these files appear as (small) text files.	delta
text	Text file	Synced as text in the workspace. Line-ending translations are performed automatically.	delta
unicode	Unicode file	Helix server operating in Unicode mode support the unicode file type. These files are translated into the local character set specified by P4CHARSET . Helix server not in Unicode mode do not support the unicode file type. For details, see the Internationalization Notes .	delta, UTF-8

Keyword	Description	Comments	Stored as
<code>utf8</code>	Unicode file	Whether the service is in Unicode mode or not, files that are detected as UTF8 will be stored as UTF8 and synced as UTF8 without being translated by the <code>P4CHARSET</code> setting. For details, see the Internationalization Notes .	delta, UTF-8
<code>utf16</code>	Unicode file	Whether the service is in Unicode mode or not, files are transferred as UTF-8, and translated to UTF-16 (with byte order mark, in the byte order appropriate for the user's computer) in the client workspace. For details, see the Internationalization Notes .	delta, UTF-8

See "Task streams" on page 90 and "Virtual streams" on page 93.

File type modifiers

You can apply file type modifiers to the base types of specific files to preserve timestamps, expand RCS keywords, specify how files are stored in the service, and more. For details about applying modifiers to file types, see "[Specifying how files are stored in Helix server](#)" on page 169.

The following table lists the file type modifiers:

Modifier	Description	Comments
<code>+C</code>	Helix server stores the full compressed version of each file revision	Default storage mechanism for <code>binary</code> files and newly-added <code>text</code> , <code>unicode</code> , or <code>utf16</code> files larger than 10MB.
<code>+D</code>	Helix server stores deltas in RCS format	Default storage mechanism for <code>text</code> files.
<code>+F</code>	Helix server stores full file per revision	For large ASCII files that aren't treated as text, such as PostScript files, where storing the deltas is not useful or efficient.

Modifier	Description	Comments
+k	RCS (Revision Control System) keyword expansion	<p>Supported keywords are as follows:</p> <hr/> <p>\$Id\$</p> <hr/> <p>\$Header\$</p> <hr/> <p>\$Date\$ Date of submission</p> <hr/> <p>\$DateUTC\$ Date of submission in UTC time zone</p> <hr/> <p>\$DateTime\$ Date and time of submission</p> <hr/> <p>\$DateTimeUTC\$ Date and time of submission in UTC time zone.</p> <hr/> <p>\$DateTimeTZ\$ Date and time of submission in the server's time zone, but including the actual time zone in the result.</p> <hr/> <p>\$Change\$</p> <hr/> <p>\$File\$</p> <hr/> <p>\$Revision\$</p> <hr/> <p>\$Author\$</p> <hr/> <p>RCS keywords are case-sensitive. A colon after the keyword (for example, \$Id: \$) is optional.</p>
+ko	Limited keyword expansion	<p>Expands only the \$Id\$ and \$Header\$ keywords. Primarily for backwards compatibility with versions of Helix server prior to 2000.1, and corresponds to the +k (ktext) modifier in earlier versions of Helix server.</p>
+l	Exclusive open (locking)	<p>If set, only one user at a time can open a file for editing.</p> <p>Useful for binary file types (such as graphics) where merging of changes from multiple authors is not possible.</p>
+m	Preserve original modification time	<p>The file's timestamp on the local file system is preserved upon submission and restored upon sync. Useful for third-party DLLs in Windows environments, because the operating system relies on the file's timestamp. By default, the modification time is set to the time you synced the file.</p>

Modifier	Description	Comments
+S	Only the head revision is stored	Older revisions are purged from the depot upon submission of new revisions. Useful for executable or <code>.obj</code> files.
+Sn	Only the most recent <code>n</code> revisions are stored, where <code>n</code> is a number from 1 to 10, or 16, 32, 64, 128, 256, or 512.	Older revisions are purged from the depot upon submission of more than <code>n</code> new revisions, or if you change an existing <code>+Sn</code> file's <code>n</code> to a number less than its current value. For details, see the Helix Core P4 Command Reference . Using an <code>+Sn</code> file modifier results in special behavior when you delete and re-add a file: no file revisions are deleted that were submitted before the add or delete. For example, if a file of type <code>+S2</code> is marked as deleted in revision 5, and then re-added with the same file type and modifier, revisions 3 and 4 are not purged.
+w	File is always writable on client	Not recommended, because Helix server manages the read-write settings on files under its control.
+x	Execute bit set on client	Used for executable files.
+X	Archive trigger required	The Helix server runs an <code>archive</code> trigger to access the file. See the Helix Core Server Administrator Guide for details.

Specifying how files are stored in Helix server

File revisions of binary files are normally stored in full within the depot, but only changes made to text files since the previous revision are normally stored. This approach is called *delta storage*, and Helix server uses RCS format to store its deltas. The file's type determines whether *full file* or *delta* storage is used.

Some file types are compressed to `gzip` format when stored in the depot. The compression occurs when you submit the file, and decompression happens when you sync (copy the file from the depot to your workspace). The client workspace always contains the file as it was submitted.

Warning

To avoid inadvertent file truncation, do not store binary files as `text`. If you store a binary file as text from a Windows computer and the file contains the Windows end-of-file character `^Z`, only the part of the file up to the `^Z` is stored in the depot.

Assigning file types for Unicode files

The Helix server can be run in Unicode mode to activate support for filenames and Helix server metadata that contain Unicode characters, or in non-Unicode mode, where filenames and metadata must be ASCII, but textual files containing Unicode content are still supported.

If you need to manage textual files that contain Unicode characters, but do not need Unicode characters in Helix server metadata, you do not need to run Helix server in Unicode mode. Assign the Helix server `utf16` file type to textual files that contain Unicode characters.

Your system administrator will be able to tell you which mode the service is using.

In either mode, Helix server supports a set of file types that enable it to determine how a file is stored and whether the file can be diffed. The following sections describe the considerations for managing textual files in Unicode environments:

To assign file type when adding a file to the depot, specify the `-t` option. For example:

```
$ p4 add -t utf16 newfile.txt
```

To change the file type of files in the depot, open the file for edit, specifying the `-t` option. For example:

```
$ p4 edit -t utf16 myfile.txt
```

Also in this section:

Choosing the file type	170
Helix server file type detection and Unicode	171

Choosing the file type

When assigning file types to textual files that contain Unicode, consider the following:

- Do you need to edit and diff the files?

Many IDEs create configuration files that you never edit manually or diff. To ensure they are never translated, assign such files the `binary` file type.
- Is your site managing files that use different character sets?

If so, consider storing them using a `utf16` file type, to ensure they are not translated but still can be diffed.

Unicode mode services translate the contents of Unicode files into the character set specified by `P4CHARSET`. The following table provides more details about how Unicode-mode services manage the various types of text files:

Text file type	Stored by Helix server as (Unicode mode)	Validated?	Translated per P4CHARSET?	Translated per client platform
<code>text</code>	Extended ASCII	No	No	No
<code>unicode</code>	UTF-8	Yes (as UTF-16 and P4CHARSET)	Yes	No
<code>utf16</code>	UTF-8	Yes (as UTF-16)	No	No

Non-Unicode-mode services do not translate or verify the contents of `unicode` files. Instead, the UTF-8 data is converted to UTF-16 using the byte order appropriate to the client platform. To ensure that such files are not corrupted when you edit them, save them as UTF-8 or UTF-16 from within your editing software.

Text file type	Stored by Helix server as (Unicode mode)	Validated?	Translated per P4CHARSET?	Translated per client platform
<code>text</code>	Extended ASCII	No	No	No
<code>unicode</code>	UTF-8	Yes (as UTF-16 and P4CHARSET)	No	No
<code>utf16</code>	UTF-8	Yes (as UTF-16)	No	Yes

Helix server file type detection and Unicode

In both Unicode mode and non-Unicode mode, if you do not assign a file type when you add a file to the depot, Helix server (by default) attempts to detect file type by scanning the first 65536 characters of the file. If non-printable characters are detected, the file is assigned the `binary` file type. (In Unicode mode, a further check is performed: if there are no non-printable characters, and there are high-ASCII characters that are translatable using the character set specified by `P4CHARSET`, the file is assigned the `unicode` file type.)

Finally (for services running in Unicode mode or non-Unicode mode), if a UTF-16 BOM is present, the file is assigned the `utf16` file type. Otherwise, the file is assigned the `text` file type. (In Unicode mode, a further check is performed: files with high-ASCII characters that are undefined in the character set specified by `P4CHARSET` are assigned the `binary` file type.)

In most cases, there is no need to override Helix server's default file type detection. If you must override Helix server's default file type detection, you can assign Helix server file types according to a file's extension, by issuing the `p4 typemap` command. For more about using the typemap feature, refer to the [Helix Core Server Administrator Guide](#), and the [Helix Core P4 Command Reference](#).

Overriding file types

Some file formats (for example, Adobe PDF files, and Rich Text Format files) are actually **binary** files, but they can be mistakenly detected by Helix server as being **text**. To prevent this problem, your system administrator can use the **p4 typemap** command to specify how such file types are stored. You can always override the file type specified in the typemap table by specifying the **-t filetype** option.

Preserving timestamps

Normally, Helix server updates the timestamp when a file is synced. The modification time (**+m**) modifier is intended for developers who need to preserve a file's original timestamp. This modifier enables you to ensure that the timestamp of a file synced to your client workspace is the time on your computer when the file was submitted.

Windows uses timestamps on third-party DLLs for versioning information (both within the development environment and also by the operating system), and the **+m** modifier enables you to preserve the original timestamps to prevent spurious version mismatches. The **+m** modifier overrides the client workspace **[no]modtime** setting (for the files to which it is applied). For details about this setting, refer to "File type modifiers" on page 167.

Expanding RCS keywords

RCS (Revision Control System), an early version control system, defined keywords that you can embed in your source files. These keywords are updated whenever a file is committed to the repository. Helix server supports some RCS keywords.

To activate RCS keyword expansion for a file, use the **+k** modifier. RCS keywords are expanded as follows.

Keyword	Expands To	Example
\$Author\$	Helix server user submitting the file	\$Author: bruno \$
\$Change\$	Helix server changelist number under which file was submitted	\$Change: 439 \$
\$Date\$	Date of last submission in format YYYY/MM/DD	\$Date: 2011/08/18 \$

Keyword	Expands To	Example
<code>\$DateTime\$</code>	Date and time of last submission in format <code>YYYY/MM/DDhh:mm:ss</code> Date and time are as of the local time on the Helix server at time of submission.	<code>\$DateTime: 2011/08/18 23:17:02 \$</code>
<code>\$File\$</code>	Filename only, in depot syntax (without revision number)	<code>\$File: //depot/path/file.txt \$</code>
<code>\$Header\$</code>	Synonymous with <code>\$Id\$</code>	<code>\$Header: //depot/path/file.txt#3 \$</code>
<code>\$Id\$</code>	Filename and revision number in depot syntax	<code>\$Id: //depot/path/file.txt#3 \$</code>
<code>\$Revision\$</code>	Helix server revision number	<code>\$Revision: #3 \$</code>

To display a file without expanding its keywords, use `p4 print -k filename`.

Helix server command syntax

This section provides basic information about **p4** commands, including command-line syntax, arguments, and options. For full details about command syntax, see the [Helix Core P4 Command Reference](#).

Certain commands require administrator or superuser permission. For details, consult the [Helix Core Server Administrator Guide](#).

You have the option of applying aliases to personal server commands, to do such things as:

- abbreviation
- creating more complex commands
- automating simple multi-command sequences
- providing alternate syntax for difficult-to-remember commands

For more information, see the "Introduction" chapter of [Helix Core P4 Command Reference](#).

Command-line syntax	174
Specifying filenames on the command line	177
Helix server wildcards	178
Restrictions on filenames and identifiers	179
Specifying file revisions	180
Reporting commands	183
Using Helix server forms	184

Command-line syntax

The basic syntax for commands is as follows:

```
p4 [global options] command [command-specific options] [command arguments]
```

The following options can be used with all **p4** commands:

Global options	Description and Example
-c <i>clientname</i>	Specifies the client workspace associated with the command. Overrides P4CLIENT . <pre>\$ p4 -c bruno_ws edit //JamCode/dev/jam/Jambase</pre>

Global options	Description and Example
-C <i>charset</i>	Specifies the client workspace's character set. Overrides P4CHARSET . \$ p4 -C utf8 sync
-d <i>directory</i>	Specifies the current directory, overriding the environment variable PWD . C:\bruno_ws> p4 -d c:\bruno_ws\dev\main\jam\Jambase Jamfile
-G	Format all output as marshaled Python dictionary objects (for scripting with Python). \$ p4 -G info
-H <i>host</i>	Specifies the hostname of the client computer, overriding P4HOST . \$ p4 -H deneb print //JamCode/dev/jam/Jambase
-I	Specify that progress indicators, if available, are desired. This option is not compatible with the -s and -G options. At present, the progress indicator is only supported by two commands: submitting a changelist with p4 -I submit and "quietly" syncing files with p4 -I sync -q .
-L <i>language</i>	Specifies the language to use for error messages from the Helix server. Overrides P4LANGUAGE . In order for this option to work, your administrator must have loaded support for non-English messages in the database. \$ p4 -L language info
-p <i>port</i>	Specifies the protocol, host and port number used to connect to the Helix server service, overriding P4PORT . \$ p4 -p ssl:deneb:1818 clients
-P <i>password</i>	Supplies a Helix server password, overriding P4PASSWD . Usually used in combination with the -u <i>username</i> option. \$ p4 -u earl -P secretpassword job
-r <i>retries</i>	Specifies the number of times to retry a command (notably, p4 sync) if the network times out.

Global options	Description and Example
-Q charset	Specifies the character set to use for command input and output; if you have set P4CHARSET to a UTF-16 or UTF-32 value, you must set P4COMMANDCHARSET to a non-UTF-16 or -32 value in order to use the p4 command-line client. \$ p4 -Q utf32 -C utf8 sync
-s	Prepend a tag to each line of output (for scripting purposes). \$ p4 -s info
-u username	Specifies a Helix server user, overriding P4USER . \$ p4 -u bill user
-x filename	Read arguments, one per line, from the specified file. To read arguments from standard input, specify -x - . \$ p4 -x myargs.txt
-z tag	To facilitate scripting, displays the output of reporting commands in the format as that generated by p4 fstat . \$ p4 -z tag info
-q	Quiet mode; suppress all informational message and report only warnings or errors.
-v	Displays the version of the p4 executable.

To display the options for a specific command, issue the **p4 help** command. For example:

```
$ p4 help add

add -- Open a new file to add it to the depot

p4 add [ -c changelist# ] [ -d -f -I -n ] [ -t filetype ] file ...

Open a file for adding to the depot. If the file exists on the
client, it is read to determine if it is text or binary. If it
does
not exist, it is assumed to be text. To be added, the file must
not
```

already reside in the depot, or it must be deleted at the current head revision. Files can be deleted and re-added.

[...]

For the full list of global options, commands, and command-specific options, see the [Helix Core P4 Command Reference](#).

Also in this section:

Specifying filenames on the command line	177
Helix server wildcards	178
Restrictions on filenames and identifiers	179
Specifying file revisions	180
Reporting commands	183

Specifying filenames on the command line

Much of your everyday use of Helix server consists of managing files. You can specify filenames in **p4** commands as follows:

- **Local syntax:** the file's name as specified in your local shell or operating system.

Filenames can be specified using an absolute path (for example, `c:\bruno_ws\dev\main\jam\fileos2.c`) or a path that is relative to the current directory (for example, `.\jam\fileos2.c`).

Relative components (`.` or `..`) cannot be specified following fixed components. For example, `mysub/mydir/./here/file.c` is invalid, because the dot (`.`) follows the fixed `mysub/mydir` components.

- **Depot syntax:** use the following format: `//depotname/file_path`, specifying the pathname of the file relative to the depot root directory. Separate the components of the path using forward slashes. For example: `//JamCode/dev/jam/Jambase`.
- **Client syntax:** use the following format: `//workspacename/file_path`, specifying the pathname of the file relative to the client root directory. Separate the components of the path using forward slashes. For example: `//ona-agave/dev/main/jam/Jambase`.

Example Using different syntaxes to refer to the same file

Local syntax:

```
C:\bruno_ws> p4 delete c:\bruno_ws\dev\main\jam\Jambase
```

Depot syntax:

```
C:\bruno_ws> p4 delete //JamCode/dev/jam/Jambase
```

Client syntax:

```
C:\bruno_ws> p4 delete //bruno_ws/dev/main/jam/Jambase
```

Helix server wildcards

For commands that operate on sets of files, Helix server supports two wildcards.

Wildcard	Description
<code>*</code>	Matches anything except slashes. Matches only within a single directory. Case sensitivity depends on your platform.
<code>...</code>	Matches anything including slashes. Matches recursively (everything in and below the specified directory).

Helix server wildcards can be used with local or Helix server syntax, as in the following examples:

Expression	Matches
<code>J*</code>	Files in the current directory starting with <code>J</code> .
<code>*/help</code>	All files called <code>help</code> in current subdirectories.
<code>./...</code>	All files under the current directory and its subdirectories.
<code>./...c</code>	All files under the current directory and its subdirectories, that end in <code>.c</code> .
<code>/usr/bruno/...</code>	All files under <code>/usr/bruno</code> .
<code>//bruno_ws/...</code>	All files in the workspace or depot that is named <code>bruno_ws</code> .
<code>//depot/...</code>	All files in the depot named <code>depot</code> .
<code>//...</code>	All files in all depots.

The `*` wildcard is expanded locally by the operating system before the command is sent to the Helix server. To prevent the local operating system from expanding the `*` wildcard, enclose it in quotes or precede it with a backslash.

Note

The `...` wildcard cannot be used with the `p4 add` command. The `...` wildcard is expanded by the Helix server, and, because the service cannot determine which files are being added, it can't expand the wildcard. The `*` wildcard can be used with `p4 add`, because it is expanded by the operating system shell and not by Helix server.

Restrictions on filenames and identifiers

Spaces in filenames, pathnames, and identifiers

Use quotation marks to enclose files or directories that contain spaces. For example:

```
"//Acme/dev/docs/manuals/recommended configuration.doc"
```

If you specify spaces in names for other Helix server objects, such as branch names, client names, label names, and so on, the spaces are automatically converted to underscores by the Helix server.

Length limitations

Names assigned to Helix server objects such as branches, client workspaces, and so on, cannot exceed 1,024 characters.

Reserved characters

By default, the following reserved characters are not allowed in Helix server identifiers or names of files managed by Helix server:

Reserved Character	Reason
@	File revision specifier for date, label name, or changelist number
#	File revision numbers
*	Wildcard
...	Wildcard (recursive)
%1 - %9	Wildcard (positional)
/	Separator for pathname components

These characters have conflicting and secondary uses. Conflicts include the following:

- UNIX separates path components with `/`, but many DOS commands interpret `/` as a command-line switch.
- Most UNIX shells interpret `#` as the beginning of a comment.
- Both DOS and UNIX shells automatically expand `*` to match multiple files, and the DOS command line uses `%` to refer to variables.

To specify these characters in filenames or paths, use the ASCII expression of the character's hexadecimal value, as shown in the following table:

Character	ASCII
@	%40
#	%23
*	%2A
%	%25

Specify the filename literally when you add it; then use the ASCII expansion to refer to it thereafter. For example, to add a file called `recommended@configuration.doc`, issue the following command:

```
$ p4 add -f //Acme/dev/docs/manuals/recommended@configuration.doc
```

When you submit the changelist, the characters are automatically expanded and appear in the change submission form as follows:

```
//Acme/dev/docs/manuals/recommended%40configuration.doc
```

After you submit the changelist with the file's addition, you must use the ASCII expansion to sync the file to your workspace or to edit it within your workspace. For example:

```
$ p4 sync //Acme/dev/docs/manuals/recommended%40configuration.doc
```

The requirement to escape the special characters @, #, *, or % also applies if you attempt to use them in the `Root:` or `AltRoots:` fields of your client specification; escape them with `%40`, `%23`, `%2A`, or `%25` respectively.

Filenames containing extended (non-ASCII) characters

Non-ASCII characters are allowed in filenames and Helix server identifiers, but entering them from the command line might require platform-specific solutions. If you are using Helix server in Unicode mode, all users must have `P4CHARSET` set properly. For details about setting `P4CHARSET`, see the [Helix Core P4 Command Reference](#) and the [Internationalization Notes](#).

In international environments, use a common code page or locale setting to ensure that all filenames are displayed consistently across all computers in your organization. To set the code page or locale:

- Windows: use the **Regional Settings** applet in the **Control Panel**
- UNIX: set the `LOCALE` environment variable

Specifying file revisions

Each time you submit a file to the depot, its revision number is incremented. To specify revisions prior to the most recent, use the # revision specifier to specify a revision number, or @ to specify a date, changelist, client workspace, or label corresponding to the version of the file you are working on. Revision specifications can be used to limit the effect of a command to specified file revisions.

Warning

Some operating system shells treat the Helix server revision character # as a comment character if it starts a word. If your shell is one of these, escape the # when you use it in **p4** commands.

The following table describes the various ways you can specify file revisions:

Revision needed	Syntax and example
Revision number	<p><i>file#n</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase#3</pre> <p>Refers to revision 3 of file Jambase</p>
The revision submitted as of a specified changelist	<p><i>file@changelist_number</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase@126</pre> <p>Refers to the version of Jambase when changelist 126 was submitted, even if it was not part of the change.</p> <pre>\$ p4 sync //JamCode/dev/...@126</pre> <p>Refers to the state of the entire depot at changelist 126 (numbered changelists are explained in "Submit a numbered changelist" on page 57).</p>
The revision in a specified label	<p><i>file@label_name</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase@beta</pre> <p>The revision of Jambase in the label called beta. For details about labels, refer to "Labels" on page 136.</p>
The revision last synced to a specified client workspace	<p><i>file@client_name</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase@bruno_ws</pre> <p>The revision of Jambase last synced to client workspace bruno_ws.</p>
Remove the file	<p><i>file#none</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase#none</pre> <p>Removes Jambase from the client workspace.</p>
The most recent version of the file	<p><i>file#head</i></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase#head</pre> <p>Same as p4 sync //JamCode/dev/jam/Jambase (If you omit the revision specifier, the head revision is synced.)</p>

Revision needed	Syntax and example
The revision last synced to your workspace	<p><code>file#have</code></p> <pre>\$ p4 files //JamCode/dev/jam/Jambase#have</pre>
The head revision of the file in the depot on the specified date	<p><code>file@date</code></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase@2011/05/18</pre> <p>The head revision of Jambase as of midnight May 18, 2011.</p>
The head revision of the file in the depot on the specified date at the specified time	<p><code>file@"date[:time]"</code></p> <pre>\$ p4 sync //JamCode/dev/jam/Jambase@"2011/05/18"</pre> <p>Specify dates in the format YYYY/MM/DD. Specify time in the format HH:MM:SS using the 24-hour clock. Time defaults to 00:00:00.</p> <p>Separate the date and the time by a single space or a colon. (If you use a space to separate the date and time, you must also enclose the entire date-time specification in double quotes.)</p>

Example Retrieving files using revision specifiers

Bruno wants to retrieve all revisions that existed at changelist number 30. He types:

```
$ p4 sync //JamCode/dev/jam/Jambase@30
```

Another user can sync their workspace so that it contains the same file revisions Bruno has synced by specifying Bruno's workspace, as follows:

```
$ p4 sync @bruno_ws
```

Example Removing all files from the client workspace

```
$ p4 sync ...#none
```

The files are removed from the workspace but not from the depot.

Date and time specifications

Date and time specifications are obtained from the time zone of the computer that hosts the Helix server. To display the date, time, offset from GMT, and time zone in effect, issue the **p4 info** command. The versioning service stores times as the number of seconds since 00:00:00 GMT Jan. 1, 1970), so if you move across time zones, the times stored in the service are correctly reported in the new time zone.

Revision ranges

Some commands can operate on a range of file revisions. To specify a revision range, specify the start and end revisions separated by a comma, for example, `#3,4`.

The commands that accept revision range specifications are:

<code>p4 annotate</code>	<code>p4 changes</code>	<code>p4 dirs</code>	<code>p4 filelog</code>	<code>p4 files</code>	<code>p4 fixes</code>	<code>p4 grep</code>	<code>p4 integrate</code>	<code>p4 interchanges</code>	<code>p4 jobs</code>	<code>p4 labels</code>	<code>p4 labelsync</code>	<code>p4 list</code>	<code>p4 merge</code>	<code>p4 print</code>	<code>p4 sizes</code>	<code>p4 sync</code>	<code>p4 tag</code>
--------------------------	-------------------------	----------------------	-------------------------	-----------------------	-----------------------	----------------------	---------------------------	------------------------------	----------------------	------------------------	---------------------------	----------------------	-----------------------	-----------------------	-----------------------	----------------------	---------------------

For the preceding commands:

- If you specify a single revision, the command operates on revision #1 through the revision you specify (except for `p4 sync`, `p4 print`, and `p4 files`, which operate on the highest revision in the range).
- If you omit the revision range entirely, the command affects all file revisions.

Example Listing changes using revision ranges

A release manager needs to see a quick list of all changes made to the jam project in July 2010. He types:

```
$ p4 changes //JamCode/dev/jam/...@2010/7/1,2010/8/1
```

The resulting list of changes looks like this:

```
Change 673 on 2010/07/31 by bruno@bruno_ws 'Final build for QA'
Change 633 on 2010/07/1 by bruno@bruno_ws 'First build w/bug fix'
Change 632 on 2010/07/1 by bruno@bruno_ws 'Started work'
```

Reporting commands

The following table lists some useful reporting commands:

To display	Use this command
A list of <code>p4</code> commands with a brief description	<code>p4 help commands</code>
Detailed help about a specific <i>command</i>	<code>p4 help command</code>
Command line options common to all Helix server commands	<code>p4 help usage</code>
Details about Helix server view syntax	<code>p4 help views</code>

To display	Use this command
All the arguments that can be specified for the <code>p4 help</code> command	<code>p4 help</code>
The Helix server settings configured for your environment	<code>p4 info</code>
The file revisions in the client workspace	<code>p4 have</code>
Preview the results of a <code>p4 sync</code> (to see which files would be transferred)	<code>p4 sync -n</code>
Preview the results of a <code>p4 delete</code> (to see which files would be marked for deletion)	<code>p4 delete -n files</code>

Using Helix server forms

Some Helix server commands, for example `p4 client` and `p4 submit`, use a text editor to display a form into which you enter the information that is required to complete the command (for example, a description of the changes you are submitting). After you change the form, save it, and exit the editor, Helix server parses the form and uses it to complete the command. (To configure the text editor that is used to display and edit Helix server forms, set `P4EDITOR`.)

When you enter information into a Helix server form, observe the following rules:

- Field names (for example, `View:`) must be flush left (not indented) and must end with a colon.
- Values (your entries) must be on the same line as the field name, or indented with tabs on the lines beneath the field name.

Some field names, such as the `Client:` field in the `p4 client` form, require a single value; other fields, such as `Description:`, take a block of text; and others, like `View:`, take a list of lines.

Certain values, like `Client:` in the client workspace form, cannot be changed. Other fields, like `Description:` in `p4 submit`, *must* be changed. If you don't change a field that needs to be changed, or vice versa, Helix server displays an error. For details about which fields can be modified, see the [Helix Core P4 Command Reference](#) or use `p4 help command`.

Glossary

A

access level

A permission assigned to a user to control which commands the user can execute. See also the 'protections' entry in this glossary and the 'p4 protect' command in the P4 Command Reference.

admin access

An access level that gives the user permission to privileged commands, usually super privileges.

APC

The Alternative PHP Cache, a free, open, and robust framework for caching and optimizing PHP intermediate code.

archive

1. For replication, versioned files (as opposed to database metadata). 2. For the 'p4 archive' command, a special depot in which to copy the server data (versioned files and metadata).

atomic change transaction

Grouping operations affecting a number of files in a single transaction. If all operations in the transaction succeed, all the files are updated. If any operation in the transaction fails, none of the files are updated.

avatar

A visual representation of a Swarm user or group. Avatars are used in Swarm to show involvement in or ownership of projects, groups, changelists, reviews, comments, etc. See also the "Gravatar" entry in this glossary.

B

base

For files: The file revision that contains the most common edits or changes among the file revisions in the source file and target file paths. For checked out streams: The public have version from which the checked out version is derived.

binary file type

A Helix server file type assigned to a non-text file. By default, the contents of each revision are stored in full, and file revision is stored in compressed format.

branch

(noun) A set of related files that exist at a specific location in the Perforce depot as a result of being copied to that location, as opposed to being added to that location. A group of related files is often referred to as a codeline. (verb) To create a codeline by copying another codeline with the 'p4 integrate', 'p4 copy', or 'p4 populate' command.

branch form

The form that appears when you use the 'p4 branch' command to create or modify a branch specification.

branch mapping

Specifies how a branch is to be created or integrated by defining the location, the files, and the exclusions of the original codeline and the target codeline. The branch mapping is used by the integration process to create and update branches.

branch view

A specification of the branching relationship between two codelines in the depot. Each branch view has a unique name and defines how files are mapped from the originating codeline to the target codeline. This is the same as branch mapping.

broker

Helix Broker, a server process that intercepts commands to the Helix server and is able to run scripts on the commands before sending them to the Helix server.

C

change review

The process of sending email to users who have registered their interest in changelists that include specified files in the depot.

changelist

A list of files, their version numbers, the changes made to the files, and a description of the changes made. A changelist is the basic unit of versioned work in Helix server. The changes specified in the changelist are not stored in the depot until the changelist is submitted to the depot. See also atomic change transaction and changelist number.

changelist form

The form that appears when you modify a changelist using the 'p4 change' command.

changelist number

An integer that identifies a changelist. Submitted changelist numbers are ordinal (increasing), but not necessarily consecutive. For example, 103, 105, 108, 109. A pending changelist number might be assigned a different value upon submission.

check in

To submit a file to the Helix server depot.

check out

To designate one or more files, or a stream, for edit.

checkpoint

A backup copy of the underlying metadata at a particular moment in time. A checkpoint can recreate db.user, db.protect, and other db.* files. See also metadata.

classic depot

A repository of Helix server files that is not streams-based. Uses the Perforce file revision model, not the graph model. The default depot name is depot. See also default depot, stream depot, and graph depot.

client form

The form you use to define a client workspace, such as with the 'p4 client' or 'p4 workspace' commands.

client name

A name that uniquely identifies the current client workspace. Client workspaces, labels, and branch specifications cannot share the same name.

client root

The topmost (root) directory of a client workspace. If two or more client workspaces are located on one machine, they should not share a client root directory.

client side

The right-hand side of a mapping within a client view, specifying where the corresponding depot files are located in the client workspace.

client workspace

Directories on your machine where you work on file revisions that are managed by Helix server. By default, this name is set to the name of the machine on which your client workspace is located, but it can be overridden. Client workspaces, labels, and branch specifications cannot share the same name.

code review

A process in Helix Swarm by which other developers can see your code, provide feedback, and approve or reject your changes.

codeline

A set of files that evolve collectively. One codeline can be branched from another, allowing each set of files to evolve separately.

comment

Feedback provided in Helix Swarm on a changelist, review, job, or a file within a changelist or review.

commit server

A server that is part of an edge/commit system that processes submitted files (checkins), global workspaces, and promoted shelves.

conflict

1. A situation where two users open the same file for edit. One user submits the file, after which the other user cannot submit unless the file is resolved. 2. A resolve where the same line is changed when merging one file into another. This type of conflict occurs when the comparison of two files to a base yields different results, indicating that the files have been changed in different ways. In this case, the merge cannot be done automatically and must be resolved manually. See file conflict.

copy up

A Helix server best practice to copy (and not merge) changes from less stable lines to more stable lines. See also merge.

counter

A numeric variable used to track variables such as changelists, checkpoints, and reviews.

CSRF

Cross-Site Request Forgery, a form of web-based attack that exploits the trust that a site has in a user's web browser.

D

default changelist

The changelist used by a file add, edit, or delete, unless a numbered changelist is specified. A default pending changelist is created automatically when a file is opened for edit.

deleted file

In Helix server, a file with its head revision marked as deleted. Older revisions of the file are still available. In Helix server, a deleted file is simply another revision of the file.

delta

The differences between two files.

depot

A file repository hosted on the server. A depot is the top-level unit of storage for versioned files (depot files or source files) within a Helix Core server. It contains all versions of all files ever submitted to the depot. There can be multiple depots on a single installation.

depot root

The topmost (root) directory for a depot.

depot side

The left side of any client view mapping, specifying the location of files in a depot.

depot syntax

Helix server syntax for specifying the location of files in the depot. Depot syntax begins with: //depot/

diff

(noun) A set of lines that do not match when two files, or stream versions, are compared. A conflict is a pair of unequal diffs between each of two files and a base, or between two versions of a stream. (verb) To compare the contents of files or file revisions, or of stream versions. See also conflict.

donor file

The file from which changes are taken when propagating changes from one file to another.

E

edge server

A replica server that is part of an edge/commit system that is able to process most read/write commands, including 'p4 integrate', and also deliver versioned files (depot files).

exclusionary access

A permission that denies access to the specified files.

exclusionary mapping

A view mapping that excludes specific files or directories.

extension

Similar to a trigger, but more modern. See "Helix Core Server Administrator Guide" on "Extensions".

F

file conflict

In a three-way file merge, a situation in which two revisions of a file differ from each other and from their base file. Also, an attempt to submit a file that is not an edit of the head revision of the file in the depot, which typically occurs when another user opens the file for edit after you have opened the file for edit.

file pattern

Helix server command line syntax that enables you to specify files using wildcards.

file repository

The master copy of all files, which is shared by all users. In Helix server, this is called the depot.

file revision

A specific version of a file within the depot. Each revision is assigned a number, in sequence. Any revision can be accessed in the depot by its revision number, preceded by a pound sign (#), for example testfile#3.

file tree

All the subdirectories and files under a given root directory.

file type

An attribute that determines how Helix server stores and diffs a particular file. Examples of file types are text and binary.

fix

A job that has been closed in a changelist.

form

A screen displayed by certain Helix server commands. For example, you use the change form to enter comments about a particular changelist to verify the affected files.

forwarding replica

A replica server that can process read-only commands and deliver versioned files (depot files). One or more replicate servers can significantly improve performance by offloading some of the master server load. In many cases, a forwarding replica can become a disaster recovery server.

G

Git Fusion

A Perforce product that integrates Git with Helix, offering enterprise-ready Git repository management, and workflows that allow Git and Helix server users to collaborate on the same projects using their preferred tools.

graph depot

A depot of type graph that is used to store Git repos in the Helix server. See also Helix4Git and classic depot.

group

A feature in Helix server that makes it easier to manage permissions for multiple users.

H

have list

The list of file revisions currently in the client workspace.

head revision

The most recent revision of a file within the depot. Because file revisions are numbered sequentially, this revision is the highest-numbered revision of that file.

heartbeat

A process that allows one server to monitor another server, such as a standby server monitoring the master server (see the p4 heartbeat command).

Helix server

The Helix server depot and metadata; also, the program that manages the depot and metadata, also called Helix Core server.

Helix TeamHub

A Perforce management platform for code and artifact repository. TeamHub offers built-in support for Git, SVN, Mercurial, Maven, and more.

Helix4Git

Perforce solution for teams using Git. Helix4Git offers both speed and scalability and supports hybrid environments consisting of Git repositories and 'classic' Helix server depots.

hybrid workspace

A workspace that maps to files stored in a depot of the classic Perforce file revision model as well as to files stored in a repo of the graph model associated with git.

I

iconv

A PHP extension that performs character set conversion, and is an interface to the GNU libiconv library.

integrate

To compare two sets of files (for example, two codeline branches) and determine which changes in one set apply to the other, determine if the changes have already been propagated, and propagate any outstanding changes from one set to another.

J

job

A user-defined unit of work tracked by Helix server. The job template determines what information is tracked. The template can be modified by the Helix server system administrator. A job describes work to be done, such as a bug fix. Associating a job with a changelist records which changes fixed the bug.

job daemon

A program that checks the Helix server machine daily to determine if any jobs are open. If so, the daemon sends an email message to interested users, informing them the number of jobs in each category, the severity of each job, and more.

job specification

A form describing the fields and possible values for each job stored in the Helix server machine.

job view

A syntax used for searching Helix server jobs.

journal

A file containing a record of every change made to the Helix server's metadata since the time of the last checkpoint. This file grows as each Helix server transaction is logged. The file should be automatically truncated and renamed into a numbered journal when a checkpoint is taken.

journal rotation

The process of renaming the current journal to a numbered journal file.

journaling

The process of recording changes made to the Helix server's metadata.

L

label

A named list of user-specified file revisions.

label view

The view that specifies which filenames in the depot can be stored in a particular label.

lazy copy

A method used by Helix server to make internal copies of files without duplicating file content in the depot. A lazy copy points to the original versioned file (depot file). Lazy copies minimize the consumption of disk space by storing references to the original file instead of copies of the file.

license file

A file that ensures that the number of Helix server users on your site does not exceed the number for which you have paid.

list access

A protection level that enables you to run reporting commands but prevents access to the contents of files.

local depot

Any depot located on the currently specified Helix server.

local syntax

The syntax for specifying a filename that is specific to an operating system.

lock

1. A file lock that prevents other clients from submitting the locked file. Files are unlocked with the 'p4 unlock' command or by submitting the changelist that contains the locked file. 2. A database lock that prevents another process from modifying the database db.* file.

log

Error output from the Helix server. To specify a log file, set the P4LOG environment variable or use the p4d -L flag when starting the service.

M

mapping

A single line in a view, consisting of a left side and a right side that specify the correspondences between files in the depot and files in a client, label, or branch. See also workspace view, branch view, and label view.

MDS checksum

The method used by Helix server to verify the integrity of versioned files (depot files).

merge

1. To create new files from existing files, preserving their ancestry (branching). 2. To propagate changes from one set of files to another. 3. The process of combining the contents of two conflicting file revisions into a single file, typically using a merge tool like P4Merge.

merge file

A file generated by the Helix server from two conflicting file revisions.

metadata

The data stored by the Helix server that describes the files in the depot, the current state of client workspaces, protections, users, labels, and branches. Metadata is stored in the Perforce database and is separate from the archive files that users submit.

modification time or modtime

The time a file was last changed.

MPM

Multi-Processing Module, a component of the Apache web server that is responsible for binding to network ports, accepting requests, and dispatch operations to handle the request.

N

nonexistent revision

A completely empty revision of any file. Syncing to a nonexistent revision of a file removes it from your workspace. An empty file revision created by deleting a file and the `#none` revision specifier are examples of nonexistent file revisions.

numbered changelist

A pending changelist to which Helix server has assigned a number.

O

opened file

A file you have checked out in your client workspace as a result of a Helix Core server operation (such as an edit, add, delete, integrate). Opening a file from your operating system file browser is not tracked by Helix Core server.

owner

The Helix server user who created a particular client, branch, or label.

P

p4

1. The Helix Core server command line program. 2. The command you issue to execute commands from the operating system command line.

p4d

The program that runs the Helix server; p4d manages depot files and metadata.

P4PHP

The PHP interface to the Helix API, which enables you to write PHP code that interacts with a Helix server machine.

PECL

PHP Extension Community Library, a library of extensions that can be added to PHP to improve and extend its functionality.

pending changelist

A changelist that has not been submitted.

Perforce

Perforce Software, Inc., a leading provider of enterprise-scale software solutions to technology developers and development operations (“DevOps”) teams requiring productivity, visibility, and scale during all phases of the development lifecycle.

project

In Helix Swarm, a group of Helix server users who are working together on a specific codebase, defined by one or more branches of code, along with options for a job filter, automated test integration, and automated deployment.

protections

The permissions stored in the Helix server’s protections table.

proxy server

A Helix server that stores versioned files. A proxy server does not perform any commands. It serves versioned files to Helix server clients.

R

RCS format

Revision Control System format. Used for storing revisions of text files in versioned files (depot files). RCS format uses reverse delta encoding for file storage. Helix server uses RCS format to store text files. See also reverse delta storage.

read access

A protection level that enables you to read the contents of files managed by Helix server but not make any changes.

remote depot

A depot located on another Helix server accessed by the current Helix server.

replica

A Helix server that contains a full or partial copy of metadata from a master Helix server. Replica servers are typically updated every second to stay synchronized with the master server.

repo

A graph depot contains one or more repos, and each repo contains files from Git users.

reresolve

The process of resolving a file after the file is resolved and before it is submitted.

resolve

The process you use to manage the differences between two revisions of a file, or two versions of a stream. You can choose to resolve file conflicts by selecting the source or target file to be submitted, by merging the contents of conflicting files, or by making additional changes. To resolve stream conflicts, you can choose to accept the public source, accept the checked out target, manually accept changes, or combine path fields of the public and checked out version while accepting all other changes made in the checked out version.

reverse delta storage

The method that Helix server uses to store revisions of text files. Helix server stores the changes between each revision and its previous revision, plus the full text of the head revision.

revert

To discard the changes you have made to a file in the client workspace before a submit.

review access

A special protections level that includes read and list accesses and grants permission to run the p4 review command.

review daemon

A program that periodically checks the Helix server machine to determine if any changelists have been submitted. If so, the daemon sends an email message to users who have subscribed to any of the files

included in those changelists, informing them of changes in files they are interested in.

revision number

A number indicating which revision of the file is being referred to, typically designated with a pound sign (#).

revision range

A range of revision numbers for a specified file, specified as the low and high end of the range. For example, `myfile#5,7` specifies revisions 5 through 7 of `myfile`.

revision specification

A suffix to a filename that specifies a particular revision of that file. Revision specifiers can be revision numbers, a revision range, change numbers, label names, date/time specifications, or client names.

RPM

RPM Package Manager. A tool, and package format, for managing the installation, updates, and removal of software packages for Linux distributions such as Red Hat Enterprise Linux, the Fedora Project, and the CentOS Project.

S

server data

The combination of server metadata (the Helix server database) and the depot files (your organization's versioned source code and binary assets).

server root

The topmost directory in which `p4d` stores its metadata (`db.*` files) and all versioned files (depot files or source files). To specify the server root, set the `P4ROOT` environment variable or use the `p4d -r` flag.

service

In the Helix Core server, the shared versioning service that responds to requests from Helix server client applications. The Helix server (`p4d`) maintains depot files and metadata describing the files and also tracks the state of client workspaces.

shelve

The process of temporarily storing files in the Helix server without checking in a changelist.

status

For a changelist, a value that indicates whether the changelist is new, pending, or submitted. For a job, a value that indicates whether the job is open, closed, or suspended. You can customize job statuses. For the 'p4 status' command, by default the files opened and the files that need to be reconciled.

storage record

An entry within the db.storage table to track references to an archive file.

stream

A "branch" with built-in rules that determines what changes should be propagated and in what order they should be propagated.

stream depot

A depot used with streams and stream clients. Has structured branching, unlike the free-form branching of a "classic" depot. Uses the Perforce file revision model, not the graph model. See also classic depot and graph depot.

stream hierarchy

The set of parent-to-child relationships between streams in a stream depot.

submit

To send a pending changelist into the Helix server depot for processing.

super access

An access level that gives the user permission to run every Helix server command, including commands that set protections, install triggers, or shut down the service for maintenance.

symlink file type

A Helix server file type assigned to symbolic links. On platforms that do not support symbolic links, symlink files appear as small text files.

sync

To copy a file revision (or set of file revisions) from the Helix server depot to a client workspace.

T

target file

The file that receives the changes from the donor file when you integrate changes between two codelines.

text file type

Helix server file type assigned to a file that contains only ASCII text, including Unicode text. See also binary file type.

theirs

The revision in the depot with which the client file (your file) is merged when you resolve a file conflict. When you are working with branched files, theirs is the donor file.

three-way merge

The process of combining three file revisions. During a three-way merge, you can identify where conflicting changes have occurred and specify how you want to resolve the conflicts.

trigger

A script that is automatically invoked by Helix server when various conditions are met. (See "Helix Core Server Administrator Guide" on "Triggers".)

two-way merge

The process of combining two file revisions. In a two-way merge, you can see differences between the files.

typemap

A table in Helix server in which you assign file types to files.

U

user

The identifier that Helix server uses to determine who is performing an operation. The three types of users are standard, service, and operator.

V

versioned file

Source files stored in the Helix server depot, including one or more revisions. Also known as an archive file. Versioned files typically use the naming convention 'filenamev' or '1.changelist.gz'.

view

A description of the relationship between two sets of files. See workspace view, label view, branch view.

W

wildcard

A special character used to match other characters in strings. The following wildcards are available in Helix server: * matches anything except a slash; ... matches anything including slashes; %%0 through %%9 is used for parameter substitution in views.

workspace

See client workspace.

workspace view

A set of mappings that specifies the correspondence between file locations in the depot and the client workspace.

write access

A protection level that enables you to run commands that alter the contents of files in the depot. Write access includes read and list accesses.

X

XSS

Cross-Site Scripting, a form of web-based attack that injects malicious code into a user's web browser.

Y

yours

The edited version of a file in your client workspace when you resolve a file. Also, the target file when you integrate a branched file.

License Statements

To get a listing of the third-party software licenses that Helix Core server uses, at the command line, type the `p4 help legal` command.

To get a listing of the third-party software licenses that the local client (such as P4V) uses, at the command line, type the `p4 help -l legal` command.